

vasm assembler system

Volker Barthelmann, Frank Wille

September 2023

Table of Contents

1	General	1
1.1	Introduction	1
1.2	Legal	1
1.3	Contact	1
1.4	Installation	1
2	The Assembler	3
2.1	General Assembler Options	3
2.2	Expressions	6
2.3	Symbols	8
2.4	Predefined Symbols	8
2.5	Include Files	8
2.6	Macros	9
2.7	Structures	9
2.8	Conditional Assembly	9
2.9	Known Problems	9
2.10	Credits	9
2.11	Error Messages	10
3	Standard Syntax Module	15
3.1	Legal	15
3.2	Additional options for this module	15
3.3	General Syntax	15
3.4	Directives	16
3.5	Known Problems	23
3.6	Error Messages	23
4	Mot Syntax Module	25
4.1	Legal	25
4.2	Additional options for this module	25
4.3	General Syntax	26
4.4	Directives	27
4.5	Known Problems	38
4.6	Error Messages	38
5	Madmac Syntax Module	41
5.1	Legal	41
5.2	General Syntax	41
5.3	Directives	41
5.4	Known Problems	45
5.5	Error Messages	45

6	Oldstyle Syntax Module	47
6.1	Legal	47
6.2	Additional options for this module	47
6.3	General Syntax	47
6.4	Directives	48
6.5	Structures	56
6.6	Known Problems	57
6.7	Error Messages	57
7	Test output module	59
7.1	Legal	59
7.2	Additional options for this module	59
7.3	General	59
7.4	Restrictions	59
7.5	Known Problems	59
7.6	Error Messages	59
8	ELF output module	61
8.1	Legal	61
8.2	Additional options for this module	61
8.3	General	61
8.4	Restrictions	61
8.5	Known Problems	61
8.6	Error Messages	61
9	a.out output module	63
9.1	Legal	63
9.2	Additional options for this module	63
9.3	General	63
9.4	Restrictions	63
9.5	Known Problems	63
9.6	Error Messages	63
10	TOS output module	65
10.1	Legal	65
10.2	Additional options for this module	65
10.3	General	65
10.4	Restrictions	65
10.5	Known Problems	66
10.6	Error Messages	66

11	GST output module	67
11.1	Legal	67
11.2	Additional options for this module	67
11.3	General	67
11.4	Restrictions	67
11.5	Known Problems	67
11.6	Error Messages	67
12	Amiga output module	69
12.1	Legal	69
12.2	Additional options for this module	69
12.3	General	69
12.4	Restrictions	70
12.5	Known Problems	70
12.6	Error Messages	70
13	X68k output module	71
13.1	Legal	71
13.2	Additional options for this module	71
13.3	General	71
13.4	Restrictions	71
13.5	Known Problems	71
13.6	Error Messages	71
14	O65 output module	73
14.1	Legal	73
14.2	Additional options for this module	73
14.3	General	74
14.4	Restrictions	74
14.5	Known Problems	74
14.6	Error Messages	74
15	vobj output module	75
15.1	Legal	75
15.2	Additional options for this module	75
15.3	General	75
15.4	Restrictions	75
15.5	Known Problems	75
15.6	Error Messages	75
16	Simple binary output module	77
16.1	Legal	77
16.2	Additional options for this module	77
16.3	General	78
16.4	Known Problems	78
16.5	Error Messages	78

17	Motorola srecord output module	79
17.1	Legal	79
17.2	Additional options for this module	79
17.3	General	79
17.4	Known Problems	79
17.5	Error Messages	79
18	Intel hex output module	81
18.1	Legal	81
18.2	Additional options for this module	81
18.3	General	81
18.4	Known Problems	81
18.5	Error Messages	81
19	C #define output module	83
19.1	Legal	83
19.2	Additional options for this module	83
19.3	General	83
19.4	Known Problems	83
19.5	Error Messages	83
20	Wozmon output module	85
20.1	Legal	85
20.2	Contact	85
20.3	Additional options for this module	85
20.4	General	85
20.5	Known Problems	85
20.6	Error Messages	85
21	m68k cpu module	87
21.1	Legal	87
21.2	Additional options for this module	87
21.2.1	CPU selections	87
21.2.2	Optimization options	88
21.2.3	Other options	90
21.3	General	91
21.4	Internal symbols	92
21.5	Extensions	93
21.6	Optimizations	97
21.6.1	Operand optimizations	97
21.6.2	Instruction optimizations	98
21.7	Known Problems	101
21.8	Error Messages	101

22	PowerPC cpu module	105
22.1	Legal	105
22.2	Additional options for this module	105
22.3	General	106
22.4	Extensions	106
22.5	Optimizations	106
22.6	Known Problems	107
22.7	Error Messages	107
23	c16x/st10 cpu module	109
23.1	Legal	109
23.2	Additional options for this module	109
23.3	General	109
23.4	Extensions	109
23.5	Optimizations	110
23.6	Known Problems	110
23.7	Error Messages	110
24	6502 cpu module	111
24.1	Legal	111
24.2	Additional options for this module	111
24.3	General	111
24.4	Extensions	112
24.5	Optimizations	113
24.6	Known Problems	113
24.7	Error Messages	113
25	ARM cpu module	115
25.1	Legal	115
25.2	Additional options for this module	115
25.3	General	116
25.4	Extensions	116
25.5	Optimizations	116
25.6	Known Problems	117
25.7	Error Messages	117
26	80x86 cpu module	119
26.1	Legal	119
26.2	Additional options for this module	119
26.3	General	119
26.4	Extensions	120
26.5	Optimizations	120
26.6	Known Problems	120
26.7	Error Messages	121

27	z80 cpu module	123
27.1	Legal	123
27.2	Additional options for this module	123
27.3	General	124
27.4	Extensions	124
27.5	Optimisations	124
27.6	Known Problems	125
27.7	Error Messages	125
28	6800 cpu module	127
28.1	Legal	127
28.2	Additional options for this module	127
28.3	General	127
28.4	Extensions	127
28.5	Optimizations	127
28.6	Known Problems	127
28.7	Error Messages	128
29	6809/6309/68HC12 cpu module	129
29.1	Legal	129
29.2	Additional options for this module	129
29.3	General	129
29.4	Extensions	129
29.5	Optimizations	130
29.6	Known Problems	130
29.7	Error Messages	130
30	Jaguar RISC cpu module	133
30.1	Legal	133
30.2	Additional options for this module	133
30.3	General	133
30.4	Optimizations	133
30.5	Extensions	133
30.6	Known Problems	134
30.7	Error Messages	134
31	PDP11 cpu module	135
31.1	Legal	135
31.2	Additional options for this module	135
31.3	General	135
31.4	Known Problems	135
31.5	Error Messages	135

32	Trillek TR3200 cpu module.....	137
32.1	Legal	137
32.2	General	137
32.3	Extensions	137
32.4	Known Problems	137
32.5	Error Messages	137
32.6	Example	138
33	Interface.....	141
33.1	Introduction	141
33.2	Building vasm.....	141
33.2.1	Directory Structure.....	141
33.2.2	Adapting the Makefile.....	141
33.2.3	Building vasm	143
33.3	vasm global variables	144
33.4	General data structures	144
33.4.1	Source	145
33.4.2	Sections	147
33.4.3	Symbols.....	148
33.4.4	Register symbols	150
33.4.5	Atoms	151
33.4.6	Relocations.....	156
33.4.7	Errors.....	157
33.5	Syntax modules	157
33.5.1	The file <code>syntax.h</code>	157
33.5.2	The file <code>syntax.c</code>	159
33.6	CPU modules	161
33.6.1	The file <code>cpu.h</code>	161
33.6.2	The file <code>cpu.c</code>	163
33.7	Output modules.....	165

1 General

1.1 Introduction

vasm is a portable and retargetable assembler able to create linkable objects in different formats as well as absolute code. Different CPU-, syntax and output-modules are supported. Most common directives/pseudo-opcodes are supported (depending on the syntax module) as well as CPU-specific extensions.

The assembler supports optimizations and relaxations (e.g. choosing the shortest possible branch instruction or addressing mode as well as converting a branch to an absolute jump if necessary).

The concept is that you get a special vasm binary for any combination of CPU- and syntax-module. All output modules, which make sense for the selected CPU, are included in the vasm binary and you have to make sure to choose the output file format you need (refer to the next chapter and look for the `-F` option). The default is a test output format, only useful for debugging or analyzing the output.

1.2 Legal

vasm is copyright in 2002-2023 by Volker Barthelmann.

This archive may be redistributed without modifications and used for non-commercial purposes.

An exception for commercial usage is granted, provided that the target CPU is M68k and the target OS is AmigaOS. Resulting binaries may be distributed commercially without further licensing.

In all other cases you need my written consent.

Certain modules may fall under additional copyrights.

1.3 Contact

Responsible for the current version of vasm and contact address in case of bug reports or support requests:

- Volker Barthelmann (vb@compilers.de)
- Frank Wille (frank@phoenix.owl.de) In case you have an issue with a specific cpu-, syntax- or output-module, please contact the module's author first, if possible.

1.4 Installation

The vasm binaries do not need additional files, so no further installation is necessary. To use vasm with vbcc, copy the binary to `vbcc/bin` after following the installation instructions for vbcc.

The vasm binaries are named `vasm<cpu>_<syntax>` with `<cpu>` representing the CPU-module and `<syntax>` the syntax-module, e.g. `vasm` for PPC with the standard syntax module is called `vasmppc_std`.

Sometimes the syntax-modifier may be omitted, e.g. `vasmppc`.

Detailed instructions how to build vasm can be found in the last chapter.

2 The Assembler

This chapter describes the module-independent part of the assembler. It documents the options and extensions which are not specific to a certain target, syntax or output driver. Be sure to also read the chapters on the cpu-backend, syntax- and output-module you are using. They will likely contain important additional information like data-representation or additional options.

2.1 General Assembler Options

`vasm` is run from the command line using the following syntax:

```
vasm<target>_<syntax> [options] [sourcefile]
```

When the source file name is missing, then the assembler reads the source text from `stdin` until EOF (end-of-file, which is CTRL-D in Unix shells, or CTRL-\ in AmigaOS shells). Note, that most debugging formats (DWARF, etc.) no longer work with such temporary source texts.

The following options are supported by the machine independent part of `vasm`:

-chklabels

Issues a warning when a label matches a mnemonic or directive name in either upper or lower case.

-D<name>[=<expression>]

Defines a symbol with the name `<name>` and assigns the value of the expression when given. The assigned value defaults to 1 otherwise.

-depend=<type>

Print all dependencies while assembling the source with the given options. No output is generated. `<type>` may be the word `list` for printing one file name in each new line, or `make` for printing a sequence of file names on a single line, suitable for Makefiles. When the output file name is given by `-o outname` then `vasm` will also print `outname:` in front of it. Note that in contrast to option `-dependall` only relative include file dependencies will be listed (which is the common case).

-dependall=<type>

Prints dependencies in the same way as `-depend`, but also prints all include files with absolute paths.

-depfile <filename>

Used together with `-depend` or `-dependall` and instructs `vasm` to output all dependencies to a new file, instead of stdout. Additionally, code will be generated in parallel to the dependencies output.

-dwarf[=<version>]

Automatically generate DWARF debugging sections, suitable for source level debugging. When the version specification is missing, DWARF V3 will be emitted. The only difference to V2 is that it creates a `.debug_ranges` section, with address ranges for all sections, instead of a bad workaround specifying `DW_AT_low_pc=0` and `DW_AT_high_pc=~0`. Note, that when you build `vasm` from

source, you may have to specify your host operating system with `-Dname` in the Makefile to include the appropriate code which can determine the current work directory. Otherwise the default would be to set the current work directory to an empty string. Currently supported are: `AMIGA`, `ATARI`, `MSDOS`, `UNIX`, `_WIN32`.

- `-esc` Enable escape character sequences. This will make vasm treat the escape character `\` in string constants similar as in the C language.
- `-F<fmt>` Use module `<fmt>` as output driver. See the chapter on output drivers for available formats and options.
- `-I<path>` Define another include path. They are searched in the order of occurrence on the command line, and always before any include paths defined in the source.
- `-ignore-mult-inc`
 When the same file is included multiple times, using the same path, this is silently ignored, causing the file to be processed only once. Note, that you can still include the same file twice when using different paths to access it.
- `-L <listfile>`
 Enables generation of a listing file and directs the output into the file `<listfile>`.
- `-Lall` List all symbols, including unused equates. Default is to list all labels and all used expressions only.
- `-Lbpl=<n>`
 Set the maximum number of bytes per line in a listing file to `<n>`. Defaults to 8 (`fmt=wide`).
- `-Lfmt=<fmt>`
 Set the listing file format to `<fmt>`. Defaults to `wide`. Available are: `wide`, `old`.
- `-Llo` Show only program labels in the sorted symbol listing. Default is to list all symbols, including absolute expressions.
- `-Lni` Do not show included source files in the listing file (`fmt=wide`).
- `-Lns` Do not include symbols in the listing file (`fmt=wide`).
- `-maxerrors=<n>`
 Sets the maximum number of errors to display before assembly is aborted. When `<n>` is 0 then there is no limit. Defaults to 5.
- `-maxmacrecurs=<n>`
 Defines the maximum number of recursion levels within a macro. Defaults to 1000.
- `-maxpasses=<n>`
 Adjusts the maximum number of passes while resolving a section. Defaults to 1500.
- `-nocase` Disables case-sensitivity for everything - identifiers, directives and instructions. Note that directives and instructions may already be case-insensitive by default in some modules.

- nocompdir** Do not search for include files relative to the compile directory (where the main input source is located).
- noesc** No escape character sequences. This will make vasm treat the escape character `\` as any other character. Might be useful for compatibility.
- noialign** Perform no automatic alignment for instructions. Note that unaligned instructions make your code crash when executed! Only set when you know what you are doing!
- nomsg=<n>** Disable the informational message `<n>`. `<n>` has to be the number of a valid informational message, like an optimization message.
- nosym** Strips all local symbols from the output file and doesn't include any other symbols than those which are required for external linkage.
- nowarn=<n>** Disable warning message `<n>`. `<n>` has to be the number of a valid warning message, otherwise an error is generated.
- o <ofile>** Write the generated assembler output to `<ofile>` rather than `a.out`.
- pad=<value>** The given padding value can be one or multiple bytes (up to the cpu-backend's address size). It is used for alignment purposes and to fill gaps between absolute ORG sections in the binary output module. Defaults to a zero-byte.
- pic** Try to generate position independent code. Every relocation entry is flagged by an error message.
- quiet** Do not print the copyright notice and the final statistics.
- unnamed-sections** Sections are no longer distinguished by their name, but only by their attributes. This has the effect that when defining a second section with a different name but same attributes as a first one, it will switch to the first, instead of starting a new section. Is set automatically, when using an output-module which doesn't support section names. For example: `aout`, `tos`, `xfile`.
- unsshift** The shift-right operator (`>>`) treats the value to shift as unsigned, which has the effect that only 0-bits are inserted on the left side. The number of bits in a value depend on the target address type (refer to the appropriate cpu module documentation).
- uspc=<value>** Uninitialized memory regions, declared by "space" directives (`.space` in std-syntax, `ds` in mot-syntax, etc.) are filled with the given value. Defaults to zero.

- w** Hide all warning messages.
- wfail** The return code of vasm will no longer be 0 (success), when there was a warning. Errors always make the return code non-zero (failure).
- v** Print version and copyright messages from the assembler and all its modules, then exit.
- x** Show an error message, when referencing an undefined symbol. The default behaviour is to declare this symbol as externally defined.

Note, that while most options allow an argument without any separating blank, some others require it (e.g. `-o` and `-L`).

2.2 Expressions

Standard expressions are usually evaluated by the main part of vasm rather than by one of the modules (unless this is necessary).

All expressions evaluated by the frontend are calculated in terms of target address values, i.e. the range depends on the backend. Constants which exceed the target address range may be supported by some backends up to 128 bits.

Backends also have the option to support floating point constants directly and convert them to a backend-specific format which is described in the backend's documentation.

Warning: Be aware that the quality and precision of the backend's floating point output depends on the combination of host- and backend-format! If you need absolute precision, encode the floating point constants yourself in binary.

The available operators include all those which are common in assembler as well as in C expressions.

C like operators:

- Unary: `+` `-` `!` `~`
- Arithmetic: `+` `-` `*` `/` `%` `<<` `>>`
- Bitwise: `&` `|` `^`
- Logical: `&&` `||`
- Comparative: `<` `>` `<=` `>=` `==` `!=`

Assembler like operators:

- Unary: `+` `-` `~`
- Arithmetic: `+` `-` `*` `/` `//` `<<` `>>`
- Bitwise: `&` `!` `~`
- Comparative: `<` `>` `<=` `>=` `=` `<>`

Up to version 1.4b the operators had the same precedence and associativity as in the C language. Newer versions have changed the operator priorities to comply with common assembler behaviour. The expression evaluation priorities, from highest to lowest, are:

1. `+` `-` `!` `~` (unary `+/-` sign, not, complement)
2. `<<` `>>` (shift left, shift right)
3. `&` (bitwise and)

4. `^ ~` (bitwise exclusive-or)
5. `| !` (bitwise inclusive-or)
6. `* / % //` (multiply, divide, modulo)
7. `+ -` (plus, minus)
8. `< > <= >=` (less, greater, less or equal, greater or equal)
9. `== != <>` (equality, inequality)
10. `&&` (logical and)
11. `||` (logical or)

Operands are integral values of the target address type. They can either be specified as integer constants of different bases (see the documentation on the syntax module to see how the base is specified) or character constants. Character constants are introduced by `'` or `"` and have to be terminated by the same character that started them.

Multiple characters are allowed and a constant is built according to the endianness of the target.

When the `-esc` option was specified, or automatically enabled by a syntax module, `vasm` interprets escape character sequences as in the C language:

<code>\\</code>	Produces a single <code>\</code> .
<code>\b</code>	The bell character.
<code>\f</code>	Form feed.
<code>\n</code>	Line feed.
<code>\r</code>	Carriage return.
<code>\t</code>	Tabulator.
<code>\"</code>	Produces a single <code>"</code> .
<code>\'</code>	Produces a single <code>'</code> .
<code>\e</code>	Escape character (27).
<code>\<octal-digits></code>	One character with the code specified by the digits as octal value.
<code>\x<hexadecimal-digits></code>	One character with the code specified by the digits as hexadecimal value.
<code>\X<hexadecimal-digits></code>	Same as <code>\x</code> .

Note, that the default behaviour of `vasm` has changed since V1.7! Escape sequence handling has been the default in older versions. This was changed to improve compatibility with other assemblers. Use `-esc` to assemble sources with escape character sequences. It is still the default in the `std` syntax module, though.

2.3 Symbols

You can define as many symbols as your available memory permits. A symbol may have any length and can be of global or local scope. Internally, there are three types of symbols:

Expression

These symbols are usually not visible outside the source, unless they are explicitly exported.

Label

Labels are always addresses within a program section. By default they have local scope for the linker.

Imported

These symbols are externally defined and must be resolved by the linker.

2.4 Predefined Symbols

Beginning with vasm V1.5c at least one expression symbol is always defined to allow conditional assembly depending on the assembler being used: `__VASM`. Its value depends on the selected cpu module.

Since V1.8i there may be a second internal symbol which reflects the format of the paths in the host file system. Currently there may be one of:

`__UNIXFS` Host file system uses Unix-style paths.

`__MSDOSFS`

Host file system uses MS-DOS-, Windows-, Atari-style paths.

`__AMIGAFS`

Host file system uses AmigaDOS-style paths.

Note that such a path-style symbol only depends on a `-D` option given while compiling vasm from source. Refer to the section about building vasm (Interface chapter) for a listing of all supported host OS options.

There may be other internal symbols, which are defined by the syntax- or by the cpu module.

2.5 Include Files

Vasm supports include files and defining include paths. Whether this functionality is available depends on the syntax module, which has to provide the appropriate directives.

On startup vasm defines one or two default include paths: the current work directory and, when the main source is not located there, the compile directory.

Include paths are searched in the following order:

1. Current work directory.
2. Compile directory (path to main source).
3. Paths specified by `-I` in the order of occurrence on the command line.
4. Paths specified by directives in the source text (in the order of occurrence).

Additionally, all the relative paths, defined by `-I` or directives, are first appended to the current work directory name, then to the compile directory name, while searching for an include file.

Searching for include files in paths based on the compile directory can be completely disabled by `-nocompdir`.

2.6 Macros

Macros are supported by `vasm`, but the directives for defining them have to be implemented in the syntax module. The assembler core supports 9 macro arguments by default to be passed in the operand field, which can be extended to any number by the syntax module. They can be referenced inside the macro either by name (`\name`) or by number (`\1` to `\9`), or both, depending on the syntax module. Recursions and early exits are supported.

Refer to the selected syntax module for more details.

2.7 Structures

Vasm supports structures, but the directives for defining them have to be implemented in the syntax module.

2.8 Conditional Assembly

Has to be provided completely by the syntax module.

2.9 Known Problems

Some known module-independent problems of `vasm` at the moment:

- None.

2.10 Credits

All those who wrote parts of the `vasm` distribution, made suggestions, answered my questions, tested `vasm`, reported errors or were otherwise involved in the development of `vasm` (in descending alphabetical order, under work, not complete):

- Jordan Zebor
- Joseph Zatarski
- Frank Wille
- Jim Westfall
- Bernard Thibault
- Jens Schönfeld
- Ross
- Henryk Richter
- Sebastian Pachuta
- Thorsten Otto
- Esben Norby
- Tom Noorduyn
- Gunther Nikl
- George Nakos
- Timm S. Mueller
- Gareth Morris
- Dominic Morris

- Garry Marshall
- Jean-Paul Mari
- Mauricio Muñoz Lucero
- Grzegorz Mazur
- Jörg van de Loo
- Robert Leffmann
- Andreas Larsson
- Miro Kropáček
- Olav Krömeke
- Christoph Krc
- Richard Körber
- Mikael Kalms
- Mark Jones
- Bert Jahn
- Daniel Illgen
- Jerome Hubert
- Matthew Hey
- Stefan Haubenthal
- Søren Hannibal
- John Hankinson
- Philippe Guichardon
- Luis Panadero Guardedeño
- Romain Giot
- Daniel Gerdgren
- François Galea
- Tom Duin
- Adrian Destugues
- Kieran Connell
- Fernando Cabrera
- Patrick Bricout
- Matthias Bock
- Simone Bevilacqua
- Karoly Balogh
- Anomie-p

2.11 Error Messages

The frontend has the following error messages:

- 1: illegal operand types
- 2: unknown mnemonic <%s>

- 3: unknown section <%s>
- 4: no current section specified
- 5: internal error %d in line %d of %s
- 6: symbol <%s> redefined
- 7: %c expected
- 8: cannot resolve section <%s>, maximum number of passes reached
- 9: instruction not supported on selected architecture
- 10: number or identifier expected
- 11: could not initialize %s module
- 12: multiple input files
- 13: could not open <%s> for input
- 14: could not open <%s> for output
- 15: unknown option <%s>
- 16:
- 17: could not initialize output module <%s>
- 18: out of memory
- 19: symbol <%s> recursively defined
- 20: fail: %s
- 21: section offset is lower than current pc
- 22: target data type overflow (%d bits)
- 23: undefined symbol <%s>
- 24: trailing garbage after option -%c
- 25: missing macro parameters
- 26: missing end directive for macro "%s"
- 27: macro definition inside macro "%s"
- 28: maximum number of %d macro arguments exceeded
- 29: option %s was specified twice
- 30: read error on <%s>
- 31: expression must be constant
- 32: initialized data in bss
- 33: missing end directive in repeat-block
- 34: #%d is not a valid warning message
- 35: relocation not allowed
- 36: illegal escape sequence \%
- 37: no current macro to exit
- 38: internal symbol %s redefined by user
- 39: illegal relocation
- 40: label name conflicts with mnemonic
- 41: label name conflicts with directive

- 42: division by zero
- 43: illegal macro argument
- 44: reloc org is already set
- 45: reloc org was not set
- 46: address space overflow
- 47: bad file-offset argument
- 48: assertion "%s" failed: %s
- 49: cannot declare structure within structure
- 50: no structure
- 51: instruction has been auto-aligned
- 52: macro name conflicts with mnemonic
- 53: macro name conflicts with directive
- 54: non-relocatable expression in equate <%s>
- 55: initialized data in offset section
- 56: illegal structure recursion
- 57: maximum number of macro recursions (%d) reached
- 58: data has been auto-aligned
- 59: register symbol <%s> redefined
- 60: cannot evaluate constant huge integer expression
- 61: cannot evaluate floating point expression
- 62: imported symbol <%s> was not referenced
- 63: symbol <%s> already defined with %s scope
- 64: unexpected "else" without "if"
- 65: unexpected "endif" without "if"
- 66: maximum if-nesting depth exceeded (%d levels)
- 67: "endif" missing for conditional block started at %s line %d
- 68: repeatedly defined symbol <%s>
- 69: macro <%s> does not exist
- 70: register <%s> does not exist
- 71: register symbol <%s> has wrong type
- 72: cannot mix positional and keyword arguments
- 73: undefined macro argument name
- 74: required macro argument %d was left out
- 75: label <%s> redefined
- 76: base %d numerical term expected
- 77: section stack overflow
- 78: section stack is empty
- 79: illegal value for option: %s
- 80: %s backend does not support floating point

- 81: unknown listing file format "%s" ignored
- 82: cannot export equate based on imported symbol: <%s>
- 83: label definition not allowed here
- 84: label defined on the same line as a new section
- 85: no debug output possible with source from stdin
- 86: external symbol <%s> must not be defined
- 87: missing definition for symbol <%s>
- 88: additional macro arguments ignored (expecting %d)

3 Standard Syntax Module

This chapter describes the standard syntax module which is available with the extension `std`.

3.1 Legal

This module is written in 2002-2023 by Volker Barthelmann and is covered by the vasm copyright without modifications.

3.2 Additional options for this module

This syntax module provides the following additional options:

- `-ac` Immediately allocate common symbols in the `.bss/.sbss` section and define them as externally visible.
- `-align` Enforces the backend's natural alignment for all data directives (`.word`, `.long`, `.float`, etc.).
- `-gas` Enable GNU-as compatibility mode. Currently this will only prevent labels prefixed by a dot to be recognized as local labels.
- `-nodotneeded` Recognize assembly directives without a leading dot (`.`).
- `-sdlimit=<n>` Put data up to a maximum size of `n` bytes into the small-data sections. Default is `n=0`, which means the function is disabled.

3.3 General Syntax

Labels always have to be terminated by a colon (`:`), therefore they don't necessarily have to start at the first column of a line.

Local labels may either be preceded by a `'.'` (unless option `-gas` was given) or terminated by `'$'`, and consist out of digits only. These labels exist and keep their value between two global label definitions.

A special form of reusable "local" labels, independent of global labels, may be defined by using a single digit from 0 to 9. You can reference the nearest previous digit-label with `Nb` and the nearest following digit-label with `Nf`, where `N` is such a digit.

Make sure that you don't define a label on the same line as a directive for conditional assembly (`if`, `else`, `endif`)! This is not supported.

The operands are separated from the mnemonic by whitespace. Multiple operands are separated by comma (`,`).

Comments are introduced by the comment character `#`. The rest of the line will be ignored. For the `c16x`, `m68k`, `650x`, `ARM`, `Z80`, `6800`, `6809`, `QNICE` and `Jaguar-RISC` backends, the comment character is `;` instead of `#`, although `#` is still allowed when being the first non-blank character on a line.

Example:

```
mylabel:  inst.q1.q2 op1,op2,op3  # comment
```

In expressions, numbers starting with 0x or 0X are hexadecimal (e.g. 0xfb2c). 0b or 0B introduces binary numbers (e.g. 0b1100101). Other numbers starting with 0 are assumed to be octal numbers, e.g. 0237. All numbers starting with a non-zero digit are decimal, e.g. 1239.

C-like escape characters in string constants are allowed by default, unless disabled by `-noesc`.

3.4 Directives

All directives are case-insensitive. The following directives are supported by this syntax module (if the CPU- and output-module allow it):

`.2byte <exp1>[,<exp2>...]`

See `.uahalf`.

`.4byte <exp1>[,<exp2>...]`

See `.uaword`.

`.8byte <exp1>[,<exp2>...]`

See `.uaquad`.

`.ascii <exp1>[,<exp2>,"<string1>"...]`

See `.byte`.

`.abort <message>`

Print an error and stop assembly immediately.

`.asciiz "<string1>"["<string2>"...]`

See `.string`.

`.align <bitorbyte_count>[,<fill>][,<maxpad>]`

Depending on the current CPU backend `.align` either behaves like `.balign` (x86) or like `.p2align` (PPC).

`.balign <byte_count>[,<fill>][,<maxpad>]`

Insert as much fill bytes as required to reach an address which is dividable by `<byte_count>`. For example `.balign 2` would make an alignment to the next 16-bit boundary. The padding bytes are initialized by `<fill>`, when given. The optional third argument defines a maximum number of padding bytes to use. When more are needed then the alignment is not done at all.

`.balignl <bit_count>[,<fill>][,<maxpad>]`

Works like `.balign`, with the only difference that the optional fill value can be specified as a 32-bit word. Padding locations which are not already 32-bit aligned, will cause a warning and padded by zero-bytes.

`.balignw <bit_count>[,<fill>][,<maxpad>]`

Works like `.balign`, with the only difference that the optional fill value can be specified as a 16-bit word. Padding locations which are not already 16-bit aligned, will cause a warning and padded by zero-bytes.

`.byte <exp1>[,<exp2>,"<string1>"...]`

Assign the integer or string constant operands into successive bytes of memory in the current section. Any combination of integer and character string constant operands is permitted.

.comm <symbol>,<size>[,<align>]
 Defines a common symbol which has a size of <size> bytes. The final size and alignment is assigned by the linker, which will use the highest size and alignment values of all common symbols with the same name found. A common symbol is usually allocated in the .bss section of the final executable. In case the optional <align> argument is not given, .comm-areas of less than 8 bytes in size are aligned to word boundaries, otherwise to doubleword boundaries.

.double <exp1>[,<exp2>...]
 Parse one or more IEEE double precision floating point expressions and write them into successive blocks of 8 bytes into memory using the backend's endianness.

.else
 Assemble the following block only if the previous .if condition was false.

.elseif <exp>
 Same as .else followed by .if, but without the need for an .endif. Avoids nesting.

.endif
 Ends a block of conditional assembly.

.endm
 Ends a macro definition.

.endr
 Ends a repetition block.

.equ <symbol>,<expression>
 See .set.

.equiv <symbol>,<expression>
 Assign the <expression> to <symbol> similar to .equ and .set, but signals an error when <symbol> has already been defined.

.err <message>
 Print a user error message. Do not create an output file.

.extern <symbol>[,<symbol>...]
 See .global.

.fail <expression>
 Cause a warning when <expression> is greater or equal 500. Otherwise cause an error.

.file "string"
 Set the filename of the input source. This may be used by some output modules. By default, the input filename passed on the command line is used.

.float <exp1>[,<exp2>...]
 Parse one or more IEEE single precision floating point expressions and write them into successive blocks of 4 bytes into memory using the backend's endianness.

.global <symbol>[,<symbol>...]
 Flag <symbol> as an external symbol, which means that <symbol> is visible to all modules in the linking process. It may be either defined or undefined.

`.globl <symbol>[,<symbol>...]`
See `.global`.

`.half <exp1>[,<exp2>...]`
Assign the values of the operands into successive 16-bit words of memory in the current section using the backend's endianness.

`.if <expression>`
Conditionally assemble the following lines if `<expression>` is non-zero.

`.ifeq <expression>`
Conditionally assemble the following lines if `<expression>` is zero.

`.ifne <expression>`
Conditionally assemble the following lines if `<expression>` is non-zero.

`.ifgt <expression>`
Conditionally assemble the following lines if `<expression>` is greater than zero.

`.ifge <expression>`
Conditionally assemble the following lines if `<expression>` is greater than zero or equal.

`.iflt <expression>`
Conditionally assemble the following lines if `<expression>` is less than zero.

`.ifle <expression>`
Conditionally assemble the following lines if `<expression>` is less than zero or equal.

`.ifb <operand>`
Conditionally assemble the following lines when `<operand>` is completely blank, except an optional comment.

`.ifnb <operand>`
Conditionally assemble the following lines when `<operand>` is non-blank.

`.ifdef <symbol>`
Conditionally assemble the following lines if `<symbol>` is defined.

`.ifndef <symbol>`
Conditionally assemble the following lines if `<symbol>` is undefined.

`.incbin <file>`
Inserts the binary contents of `<file>` into the object code at this position.

`.incdir <path>`
Add another path to search for include files to the list of known paths. Paths defined with `-I` on the command line are searched first.

`.include <file>`
Include source text of `<file>` at this position.

`.int <exp1>[,<exp2>...]`
Assign the values of the operands into successive words of memory in the current section using the target's endianness and address size.

- .irp <symbol>[,<val>...]**
 Iterates the block between **.irp** and **.endr** for each <val>. The current <val>, which may be embedded in quotes, is assigned to **\symbol**. If no value is given, then the block is assembled once, with **\symbol** set to an empty string.
- .irpc <symbol>[,<val>...]**
 Iterates the block between **.irp** and **.endr** for each character in each <val>, and assign it to **\symbol**. If no value is given, then the block is assembled once, with **\symbol** set to an empty string.
- .lcomm <symbol>,<size>[,<alignment>]**
 Allocate <size> bytes of space in the .bss section and assign the value to that location to <symbol>. If <alignment> is given, then the space will be aligned to an address having <alignment> low zero bits or 2, whichever is greater. <symbol> may be made globally visible by the **.globl** directive.
- .list** The following lines will appear in the listing file, when enabled.
- .local <symbol>[,<symbol>...]**
 Flag <symbol> as a local symbol, which means that <symbol> is local for the current file and invisible to other modules in the linking process.
- .long <exp1>[,<exp2>...]**
 Assign the values of the operands into successive 32-bit words of memory in the current section using the backend's endianness.
- .macro <name> [<argname1>[=<default>] [<argname2>...]]**
 Defines a macro, which can be referenced by <name>. The macro definition is closed by an **.endm** directive. The argument names, which may be passed to this macro, must be declared directly following the macro name, separated by white-space. You can define an optional default value in the case an argument is left out. Note that macro names are case-insensitive while the argument names are case-sensitive. Within the macro context arguments are referenced by **\argname**. The special argument **\@** inserts a unique id, useful for defining labels. **\()** may be used as a separator between the name of a macro argument and the subsequent text.
- .nolist** The following lines will not be visible in a listing file.
- .org <exp>[,<fill>]**
 Before any other section directive <exp> defines the absolute start address of the program. Within a section <exp> defines the offset from the start of this section for the subsequent code. The optional <fill> value is only valid within a section and is used to fill the space to the new program counter (defaults to zero). When <exp> starts with a current-pc symbol followed by a plus (+) operator, then the directive just reserves space (filled with zero).
- .p2align <bit_count>[,<fill>] [,<maxpad>]**
 Insert as much fill bytes as required to reach an address where <bit_count> low order bits are zero. For example **.p2align 2** would make an alignment to the next 32-bit boundary. The padding bytes are initialized by <fill>, when given. The optional third argument defines a maximum number of padding bytes to use. When more are needed then the alignment is not done at all.

.p2alignl <bit_count>[,<fill>][,<maxpad>]

Works like **.p2align**, with the only difference that the optional fill value can be specified as a 32-bit word. Padding locations which are not already 32-bit aligned, will cause a warning and padded by zero-bytes.

.p2alignw <bit_count>[,<fill>][,<maxpad>]

Works like **.p2align**, with the only difference that the optional fill value can be specified as a 16-bit word. Padding locations which are not already 16-bit aligned, will cause a warning and padded by zero-bytes.

.popsection

Restore the top section from the internal section-stack. Also refer to **.pushsection**.

.pushsection <name>[, "<attributes>"][[,@<type>]][[,%<type>]][[,<mem_flags>]]

Works exactly like **.section**, but additionally pushes the previously active section onto an internal stack, where it may be restored from by the **.popsection** directive.

.quad <exp1>[,<exp2>...]

Assign the values of the operands into successive quadwords (64-bit) of memory in the current section using the backend's endianness.

.rept <expression>

Repeats the assembly of the block between **.rept** and **.endr** <expression> number of times. <expression> has to be positive.

.section <name>[, "<attributes>"][[,@<type>]][[,%<type>]][[,<mem_flags>]]

Starts a new section named <name> or reactivate an old one. If attributes are given for an already existing section, they must match exactly. The section's name will also be defined as a new symbol, which represents the section's start address. The "<attributes>" string may consist of the following characters:

Section Contents:

c	section has code
d	section has initialized data
u	section has uninitialized data
i	section has directives (info or offsets section)
n	section can be discarded
R	remove section at link time
a	section is allocated in memory

Section Protection:

r	section is readable
w	section is writable
x	section is executable
s	section is shareable

Section Alignment: A digit, which is ignored. The assembler will automatically align the section to the highest alignment restriction used within.

Memory flags (Amiga hunk format only):

C load section to Chip RAM

F load section to Fast RAM

The optional `<type>` argument is mainly used for ELF output and may be introduced either by a `'%'` or a `'@'` character. Allowed are:

progbits This is the default value, which means the section data occupies space in the file and may have initialized data.

nobits These sections do not occupy any space in the file and will be allocated filled with zero bytes by the OS loader.

When the optional, non-standard, `<mem_flags>` argument is given it defines a 32-bit memory attribute, which defines where to load the section (platform specific). The memory attributes are currently only used in the hunk-format output module.

.set <symbol>,<expression>

Create a new program symbol with the name `<symbol>` and assign to it the value of `<expression>`. If `<symbol>` is already assigned, it will contain a new value from now on.

.size <symbol>,<size>

Set the size in bytes of an object defined at `<symbol>`.

.short <exp1>[,<exp2>...]

Assign the values of the operands into successive 16-bit words of memory in the current section using the backend's endianness.

.single <exp1>[,<exp2>...]

Parse one or more IEEE single precision floating point expressions and write them into successive blocks of 4 bytes into memory using the backend's endianness.

.skip <exp>[,<fill>]

Insert `<exp>` zero or `<fill>` bytes into the current section.

.space <exp>[,<fill>]

Insert `<exp>` zero or `<fill>` bytes into the current section.

.stabs "<name>",<type>,<other>,<desc>,<exp>

Add an stab-entry for debugging, including a symbol-string and an expression.

.stabn <type>,<other>,<desc>,<exp>

Add an stab-entry for debugging, without a symbol-string.

.stabd <type>,<other>,<desc>

Add an stab-entry for debugging, without symbol-string and value.

.string "<string1>"[, "<string2>"...]

Like `.byte`, but adds a terminating zero-byte.

.swbeg <op>

Just for compatibility. Do nothing.

.type <symbol>,<type>

Set type of symbol named <symbol> to <type>, which must be one of:

1: **Object**

2: **Function**

3: **Section**

4: **File**

The predefined symbols **@object** and **@function** are available for this purpose.

.uahalf <exp1>[,<exp2>...]

Assign the values of the operands into successive 16-bit areas of memory in the current section regardless of current alignment.

.ualong <exp1>[,<exp2>...]

Assign the values of the operands into successive 32-bit areas of memory in the current section regardless of current alignment.

.uaquad <exp1>[,<exp2>...]

Assign the values of the operands into successive 64-bit areas of memory in the current section regardless of current alignment.

.uashort <exp1>[,<exp2>...]

Assign the values of the operands into successive 16-bit areas of memory in the current section regardless of current alignment.

.uaword <exp1>[,<exp2>...]

Assign the values of the operands into successive 16-bit areas of memory in the current section regardless of current alignment.

.weak <symbol>[,<symbol>...]

Flag <symbol> as a weak symbol, which means that <symbol> is visible to all modules in the linking process and may be replaced by any global symbol with the same name. When a weak symbol remains undefined its value defaults to 0.

.word <exp1>[,<exp2>...]

Assign the values of the operands into successive 16-bit words of memory in the current section using the backend's endianness.

.zero <exp>[,<fill>]

Insert <exp> zero or <fill> bytes into the current section.

Predefined section directives:

.bss .section ".bss","aurw"

.data .section ".data","adrw"

.rodata .section ".rodata","adr"

.sbss .section ".sbss","aurw"


```
.sdata    .section ".sdata","adrw"  
.sdata2   .section ".sdata2","adr"  
.stab     .section ".stab","dr"  
.stabstr  .section ".stabstr","dr"  
.text     .section ".text","acrx"  
.tocd     .section ".tocd","adrw"  
.dpage    .section ".dpage","adrw"
```

3.5 Known Problems

Some known problems of this module at the moment:

- None.

3.6 Error Messages

This module has the following error messages:

- 1001: mnemonic expected
- 1002: invalid extension
- 1003: no space before operands
- 1004: too many closing parentheses
- 1005: missing closing parentheses
- 1006: missing operand
- 1007: scratch at end of line
- 1008: section flags expected
- 1009: invalid data operand
- 1010: memory flags expected
- 1011: identifier expected
- 1012: assembly aborted
- 1013: unexpected "%s" without "%s"
- 1014: pointless default value for required parameter <%s>
- 1015: invalid section type ignored, assuming progbits
- 1019: syntax error
- 1021: section name expected
- 1022: .fail %lld encountered
- 1023: .fail %lld encountered
- 1024: alignment too big

4 Mot Syntax Module

This chapter describes the Motorola syntax module, mostly used for the M68k and ColdFire families of CPUs, which is available with the extension `mot`.

4.1 Legal

This module is written in 2002-2023 by Frank Wille and is covered by the vasm copyright without modifications.

4.2 Additional options for this module

This syntax module provides the following additional options:

- align** Enables natural alignment for data (e.g. `dc`, `ds`) and offset directives (`rs`, `so`, `fo`).
- allmp** Makes all 35 macro arguments available. Default are 9 arguments (`\1` to `\9`). More arguments can be accessed through `\a` to `\z`), which may conflict with escape characters or named arguments, therefore they are not enabled by default.
- cnop=<code>**
 Sets a two-byte code used for alignment padding with `cnop` in code sections. Defaults to `0x4e71` on M68k.
- devpac** Devpac-compatibility mode. Only directives known to Devpac are recognized.
 - Enables natural alignment for data and structure offsets (see option `-align`).
 - Predefines offset symbols `__RS`, `__SO` and `__FO` as 0, which otherwise are undefined until first referenced.
 - Disable escape codes handling in strings (see `-noesc`).
 - Enable dots within identifiers (see `-ldots`).
 - Up to 35 macro arguments (see `-allmp`).
 - Do not use NOP instructions when aligning code (see `-cnop=`).
 - Allow a label definition on the same line as a section directive. Note, that in contrast to Devpac this label is not ignored but set to the first address in the section!
- ldots** Allow dots (`.`) within all identifiers.
- localu** Local symbols are prefixed by `'_'` instead of `'.'`. For Devpac compatibility, which offers a similar option.
- nolocpfx**
 Disables local symbols to be recognized by their prefix (usually `'.'`). This allows global symbols to be defined with it. The `'$'` suffix for local symbols still works.
- phxass** PhxAss-compatibility mode. Only directives known to PhxAss are recognized.
 - Enable escape codes handling in strings (see `-esc`).

- Macro names are treated as case-insensitive.
 - Up to 35 macro arguments (see `-allmp`).
 - Allow whitespace in operands.
 - Enable dots within identifiers (see `-ldots`).
 - Defines the symbol `_PHXASS_` with value 2 (to differentiate from the real PhxAss with value 1).
 - When no output file name is given, construct it from the input name.
 - Allow a label definition on the same line as a section directive.
- spaces** Allow whitespace characters in the operand field. Otherwise a whitespace would start the comment field there.
- warncomm** Warn about all lines, which have comments in the operand field, introduced by a whitespace character. For example in: `dc.w 1 + 2.`

4.3 General Syntax

Labels must either start at the first column of a line or have to be terminated by a colon (:). In the first case the mnemonic has to be separated from the label by whitespace (not required in any case, e.g. with the `=` directive). A double colon (::) automatically makes the label externally visible (see also `xdef`).

Local labels are either prefixed by `'.'` or suffixed by `'$'`. For the rest, any alphanumeric character including `'_'` is allowed. Local labels are valid between two global label definitions.

Otherwise dots (.) are not allowed within a label by default, unless the option `-ldots` or `-devpac` was specified. Even then, labels ending on `.b`, `.w` or `.l` can't be defined.

It is possible to refer to any local symbol in the source by preceding its name with the name of the last previously defined global symbol: `global_name\local_name`. This is for PhxAss compatibility only, and is no recommended style. Does not work in a macro, as it conflicts with macro arguments.

Make sure that you don't define a label on the same line as a directive for conditional assembly (`if`, `else`, `endif`)! This is not supported.

Qualifiers are appended to the mnemonic, separated by a dot (if the CPU-module supports qualifiers). The operands are separated from the mnemonic by whitespace. Multiple operands are separated by comma (,).

In this syntax module, the operand field must not contain any whitespace characters, as long as the option `-spaces` was not specified.

Comments can be introduced everywhere by the characters `;` or `*`. The rest of the line will be ignored. Also everything following the operand field, separated by a whitespace, will be regarded as comment (unless `-spaces` was given). Be careful with `*`, which is either recognized as the "current pc symbol" or as a multiplication operation in any operand expression

Example:

```
mylabel inst.q op1,op2,op3 ;comment
```

In expressions, numbers starting with \$ are hexadecimal (e.g. \$fb2c). % introduces binary numbers (e.g. %1100101). Numbers starting with @ are assumed to be octal numbers, e.g. @237. All numbers starting with a digit are decimal, e.g. 1239.

4.4 Directives

The following directives are supported by this syntax module (provided the CPU- and output-module support them):

```
<symbol> = <expression>
    Equivalent to <symbol> equ <expression>.

<symbol> =.s <expression>
    Equivalent to <symbol> fequ.s <expression>. PhxAss compatibility.

<symbol> =.d <expression>
    Equivalent to <symbol> fequ.d <expression>. PhxAss compatibility.

<symbol> =.x <expression>
    Equivalent to <symbol> fequ.x <expression>. PhxAss compatibility.

<symbol> =.p <expression>
    Equivalent to <symbol> fequ.p <expression>. PhxAss compatibility.

align <bitcount>
    Insert as many zero bytes as required to reach an address where <bitcount> low
    order bits are zero. For example align 2 would make an alignment to the next
    32-bit boundary.

assert <expression>[,<message>]
    Display an error with the optional <message> when the expression is false.

blk.b <exp>[,<fill>]
    Equivalent to dcb.b <exp>,<fill>.

blk.d <exp>[,<fill>]
    Equivalent to dcb.d <exp>,<fill>.

blk.l <exp>[,<fill>]
    Equivalent to dcb.l <exp>,<fill>.

blk.q <exp>[,<fill>]
    Equivalent to dcb.q <exp>,<fill>.

blk.s <exp>[,<fill>]
    Equivalent to dcb.s <exp>,<fill>.

blk.w <exp>[,<fill>]
    Equivalent to dcb.w <exp>,<fill>.

blk.x <exp>[,<fill>]
    Equivalent to dcb.x <exp>,<fill>.

bss      Equivalent to section bss,bss.

bss_c    Equivalent to section bss_c,bss,chip.
```

- bss_f** Equivalent to `section bss_f,bss,fast`.
- cargs** [**#**<offset>,<symbol1>[.<size1>][,<symbol2>[.<size2>]]...
 Defines <symbol1> with the value of <offset>. Further symbols on the line, separated by comma, will be assigned the <offset> plus the size of the previous symbol. The size defaults to 2. Valid optional size extensions are: `.b`, `.w`, `.l`, where `.l` results in a size of 4, the others 2. The <offset> argument defaults to the target's address size (4 for M68k) when omitted.
- clrfo** Reset stack-frame offset counter to zero. See `fo` directive.
- clrso** Reset structure offset counter to zero. See `so` directive.
- cnop** <offset>,<alignment>
 Insert as many padding bytes as required to reach an address which can be divided by <alignment>. Then add <offset> padding bytes. May fill the padding-bytes with no-operation instructions for certain cpus.
- code** Equivalent to `section code,code`.
- code_c** Equivalent to `section code_c,code,chip`.
- code_f** Equivalent to `section code_f,code,fast`.
- comm** <symbol>,<size>
 Create a common symbol with the given size. The alignment is always 32 bits.
- comment** Starting with the operand field everything is ignored and seen as a comment. There is only one exception, when the operand contains `HEAD=`. Then the following expression is passed to the TOS output module via the symbol '`TOSFLAGS`', to define the Atari specific TOS flags.
- cseg** Equivalent to `section code,code`.
- data** Equivalent to `section data,data`.
- data_c** Equivalent to `section data_c,data,chip`.
- data_f** Equivalent to `section data_f,data,fast`.
- db** <exp1>[,<exp2>,"<string1>",<string2>']...]
 Equivalent to `dc.b` for ArgAsm, BAsm, HX68, Macro68, ProAsm, etc. compatibility. Does not exist in PhxAss- or Devpac-compatibility mode.
- dc.b** <exp1>[,<exp2>,"<string1>",<string2>']...]
 Assign the integer or string constant operands into successive bytes of memory in the current section. Any combination of integer and character string constant operands is permitted.
- dc.d** <exp1>[,<exp2>...]
 Assign the values of the operands into successive 64-bit words of memory in the current section, using the IEEE double precision format when specifying them as floating point constants.
- dc.l** <exp1>[,<exp2>...]
 Assign the values of the operands into successive 32-bit words of memory in the current section.

`dc.p <exp1>[,<exp2>...]`

Assign the values of the operands into successive 96-bit words of memory in the current section, using the Packed Decimal format when specifying them as floating point constants.

`dc.q <exp1>[,<exp2>...]`

Assign the values of the operands into successive 64-bit words of memory in the current section.

`dc.s <exp1>[,<exp2>...]`

Assign the values of the operands into successive 32-bit words of memory in the current section, using the IEEE single precision format when specifying them as floating point constants.

`dc.w <exp1>[,<exp2>...]`

Assign the values of the operands into successive 16-bit words of memory in the current section.

`dc.x <exp1>[,<exp2>...]`

Assign the values of the operands into successive 96-bit words of memory in the current section, using the IEEE extended precision format when specifying them as floating point constants.

`dcb.b <exp>[,<fill>]`

Insert <exp> zero or <fill> bytes into the current section.

`dcb.d <exp>[,<fill>]`

Insert <exp> zero or <fill> 64-bit words into the current section. <fill> may also be a floating point constant which is then written in IEEE double precision format.

`dcb.l <exp>[,<fill>]`

Insert <exp> zero or <fill> 32-bit words into the current section.

`dcb.q <exp>[,<fill>]`

Insert <exp> zero or <fill> 64-bit words into the current section.

`dcb.s <exp>[,<fill>]`

Insert <exp> zero or <fill> 32-bit words into the current section. <fill> may also be a floating point constant which is then written in IEEE single precision format.

`dcb.w <exp>[,<fill>]`

Insert <exp> zero or <fill> 16-bit words into the current section.

`dcb.x <exp>[,<fill>]`

Insert <exp> zero or <fill> 96-bit words into the current section. <fill> may also be a floating point constant which is then written in IEEE extended precision format.

`dl <exp1>[,<exp2>...]`

Equivalent to `dc.l` for ArgAsm, BAsm, HX68, Macro68, ProAsm, etc. compatibility. Does not exist in PhxAss- or Devpac-compatibility mode.

- dr.b** <exp1>[,<exp2>...]
 Calculates <expN> - <current pc value> and stores it into successive bytes of memory in the current section.
- dr.w** <exp1>[,<exp2>...]
 Calculates <expN> - <current pc value> and stores it into successive 16-bit words of memory in the current section.
- dr.l** <exp1>[,<exp2>...]
 Calculates <expN> - <current pc value> and stores it into successive 32-bit words of memory in the current section.
- ds.b** <exp>
 Equivalent to **dcb.b** <exp>,0.
- ds.d** <exp>
 Equivalent to **dcb.d** <exp>,0.
- ds.l** <exp>
 Equivalent to **dcb.l** <exp>,0.
- ds.q** <exp>
 Equivalent to **dcb.q** <exp>,0.
- ds.s** <exp>
 Equivalent to **dcb.s** <exp>,0.
- ds.w** <exp>
 Equivalent to **dcb.w** <exp>,0.
- ds.x** <exp>
 Equivalent to **dcb.x** <exp>,0.
- dseg** Equivalent to **section data,data**.
- dw** <exp1>[,<exp2>...]
 Equivalent to **dc.w** for ArgAsm, BAsm, HX68, Macro68, ProAsm, etc. compatibility. Does not exist in PhxAss- or Devpac-compatibility mode.
- dx.b** <exp>
 Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to **dcb.b** <exp>,0.
- dx.d** <exp>
 Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to **dcb.d** <exp>,0.
- dx.l** <exp>
 Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to **dcb.l** <exp>,0.
- dx.q** <exp>
 Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to **dcb.q** <exp>,0.

<code>dx.s <exp></code>	Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to <code>dcb.s <exp>,0</code> .
<code>dx.w <exp></code>	Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to <code>dcb.w <exp>,0</code> .
<code>dx.x <exp></code>	Tries to allocate space in the DataBss portion of a code or data section. Otherwise equivalent to <code>dcb.x <exp>,0</code> .
<code>echo <"string" exp>[,<"string" exp>]...</code>	Prints one or more strings or expressions to stdout, terminated by a newline. Strings are identified by single- or double-quotes. In PhxAss-compatibility mode only a single string can be printed.
<code>inline</code>	End a block of isolated local labels, started by <code>inline</code> .
<code>else</code>	Assemble the following lines if the previous <code>if</code> condition was false.
<code>elseif</code>	Same as <code>else</code> , for compatibility!
<code>elif <exp></code>	This is a real else-if directive! Not supported by Devpac. It's the same as <code>else</code> followed by <code>if</code> , but without the need for a matching <code>endif</code> directive. Avoids nesting.
<code>end</code>	Assembly will terminate with this line. The subsequent source text is ignored.
<code>endif</code>	Ends a section of conditional assembly.
<code>endm</code>	Ends a macro definition.
<code>endr</code>	Ends a repetition block.
<code><symbol> equ <expression></code>	Define a new program symbol with the name <code><symbol></code> and assign to it the value of <code><expression></code> . Defining <code><symbol></code> twice will cause an error.
<code><symbol> equ.s <expression></code>	Equivalent to <code><symbol> fequ.s <expression></code> . PhxAss compatibility.
<code><symbol> equ.d <expression></code>	Equivalent to <code><symbol> fequ.d <expression></code> . PhxAss compatibility.
<code><symbol> equ.x <expression></code>	Equivalent to <code><symbol> fequ.x <expression></code> . PhxAss compatibility.
<code><symbol> equ.p <expression></code>	Equivalent to <code><symbol> fequ.p <expression></code> . PhxAss compatibility.
<code>erem</code>	Ends an outcommented block. Assembly will continue.
<code>even</code>	Aligns to an even address. Equivalent to <code>cnop 0,2</code> .
<code>fail <message></code>	Show an error message including the <code><message></code> string. Do not generate an output file.

<symbol> fequ.s <expression>

Define a new program symbol with the name <symbol> and assign to it the floating point value of <expression>. Defining <symbol> twice will cause an error. The extension is for Devpac-compatibility, but will be ignored.

<symbol> fequ.d <expression>

Equivalent to <symbol> fequ.s <expression>.

<symbol> fequ.x <expression>

Equivalent to <symbol> fequ.s <expression>.

<symbol> fequ.p <expression>

Equivalent to <symbol> fequ.s <expression>.

<label> fo.<size> <expression>

Assigns the current value of the stack-frame offset counter to <label>. Afterwards the counter is decremented by the instruction's <size> multiplied by <expression>. Any valid M68k size extension is allowed for <size>: b, w, l, q, s, d, x, p. The offset counter can also be referenced directly under the name __F0.

idnt <name>

Sets the file or module name in the generated object file to <name>, when the selected output module supports it. By default, the input filename passed on the command line is used.

if <expression>

Conditionally assemble the following lines if <expression> is non-zero.

if1

Just for compatibility. Not really supported, as vasm parses a source text only once. Always true.

if2

Just for compatibility. Not really supported, as vasm parses a source text only once. Always false.

ifeq <expression>

Conditionally assemble the following lines if <expression> is zero.

ifne <expression>

Conditionally assemble the following lines if <expression> is non-zero.

ifgt <expression>

Conditionally assemble the following lines if <expression> is greater than zero.

ifge <expression>

Conditionally assemble the following lines if <expression> is greater than zero or equal.

iflt <expression>

Conditionally assemble the following lines if <expression> is less than zero.

ifle <expression>

Conditionally assemble the following lines if <expression> is less than zero or equal.

ifb <operand>

Conditionally assemble the following lines when <operand> is completely blank, except for an optional comment.

ifnb <operand>

Conditionally assemble the following lines when <operand> is non-blank.

ifc <string1>,<string2>

Conditionally assemble the following lines if <string1> matches <string2>.

ifnc <string1>,<string2>

Conditionally assemble the following lines if <string1> does not match <string2>.

ifd <symbol>

Conditionally assemble the following lines if <symbol> is defined.

ifnd <symbol>

Conditionally assemble the following lines if <symbol> is undefined.

ifmacro <macro>

Conditionally assemble the following line if <macro> is defined.

ifmacro <macro>

Conditionally assemble the following line if <macro> is undefined.

ifp1 Just for compatibility. Equivalent to **if1**.

iif <expression> <statement>

Conditionally assemble the <statement> following <expression>. IIF stands for Immediate IF. If the value of <expression> is non-zero then <statement> is assembled. No **ENDC** must be used in conjunction with this directive. The <statement> cannot include a label, but a label may precede the IIF directive. For example:

```
foo IIF bar equ 42
```

The **foo** label will be assigned with 42 if **bar** evaluates to true, otherwise **foo** will be assigned with the current program counter. Assigning a value in the IIF <statement> using the equal (=) operator, while the option **-spaces** was given, cannot work, because the equal operator will be evaluated as part of the expression. I.e. **foo IIF 1+1 = 42** works, but **foo IIF 1 + 1 = 42**, when the option **-spaces** was specified, won't, as **= 42** is evaluated as part of the expression.

incbin <filename>[,<offset>[,<length>]]

Inserts the binary contents of <filename> into the object code at this position. When <offset> is specified, then the given number of bytes will be skipped at the beginning of the file. The optional <length> argument specifies the maximum number of bytes to be read from that file.

incdir <path>

Add another path to search for include files to the list of known paths. Paths defined with **-I** on the command line are searched first.

- include** <filename>
 Include source text of <filename> at this position. When the file name specified has no absolute path, then search it in all defined paths in the order of occurrence, starting with the current work directory.
- inline**
 Local labels in the following block are isolated from previous local labels and those after **einline**.
- list**
 The following lines will appear in the listing file, if it was requested.
- llen** <len>
 Set the line length in a listing file to a maximum of <len> characters. Currently without any effect.
- local**
 Separates two blocks of local labels. Which means, local labels from above this directive may be reused.
- macro** <name>
 Defines a macro which can be referenced by <name>. For compatibility, the <name> may alternatively appear on the left side of the **macro** directive, starting on the first column. Then the operand field is ignored. The macro definition is terminated by an **endm** directive. When calling a macro you may pass up to 9 arguments, separated by comma. These arguments are referenced within the macro context as \1 to \9. Parameter \0 is set to the macro's first qualifier (mnemonic extension), when given. In Devpac- and PhxAss-compatibility mode, or with option **-allmp**, up to 35 arguments are accepted, where argument 10-35 can be referenced by \a to \z. In case you have a macro argument which contains commas or spaces you may enclose it between < and > characters. A > character may still be included by writing >>, or when embedded within a string. (Note that strings are ignored in Devpac compatibility mode.)
- Special macro parameters:
- \@ Insert a unique id, useful for defining labels. Every macro call gets its own unique id.
 - \@! Push the current unique id onto a global id stack, then insert it.
 - \@? Push the current unique id below the top element of the global id stack, then insert it.
 - \@@ Pull the top element from the global id stack and insert it. The macro's current unique id is not affected by this operation.
 - \# Insert the number of arguments that have been passed to this macro. Equivalent to the contents of the symbol **NARG**.
 - \?n Insert the length of the n'th macro argument.
 - \. Insert the argument which is selected by the current value of the **CARG** symbol (first argument, when **CARG** is 1).
 - \+ Works like \., but increments the value of **CARG** after that.
 - \- Works like \., but decrements the value of **CARG** after that.

- `\<symbolname>`
 Inserts the current decimal value of the absolute symbol `symbolname`.
- `\<$symbolname>`
 Inserts the current hexadecimal value of the absolute symbol `symbolname`, without leading \$.
- mexit** Leave the current macro and continue with assembling the parent context. Note that this directive also resets the level of conditional assembly to a state before the macro was invoked; which means that it also works as a 'break' command on all new `if` directives.
- msource on/off**
 Enable or disable source level debugging within a macro context. It can be used before one or more macro definitions. When off, the debugger will show the invoking source text line instead. Defaults to **on**. Also numeric expressions like 0 or 1 are allowed. Note, that this directive currently only has a meaning when using the `-linedebug` option with the hunk-format output module (`-Fhunk`).
- nolist** The following lines will not be visible in a listing file.
- nopage** Never start a new page in the listing file. This implementation will only prevent emitting the formfeed code.
- nref <symbol>[,<symbol>...]**
 Flag `<symbol>` as externally defined, similar to `xref`, but also indicate that references can be optimized to base-relative addressing modes, when possible. This directive is only present in PhxAss-compatibility mode.
- odd** Aligns to an odd address. Equivalent to `cnop 1,2`. Bugs: Note that this is not a real `odd` directive, as it wastes two bytes when the address is already odd.
- offset [<expression>]**
 Switches to a special offset-section, similar to a `section` directive, although its contents is not included in the output. Its labels may be referenced as absolute offset symbols. Can be used to define structure offsets. The optional `<expression>` gives the start offset for this section. When missing, the last offset of the previous offset-section is used, or 0. `<expression>` must evaluate as a constant!
- org <expression>**
 Sets the base address for the subsequent code. Note that it is allowed to embed such an absolute `ORG` block into a section. Return to relocatable mode with any new `section` directive. Although, in Devpac compatibility mode the previous section will stay absolute.
- output <name>**
 Sets the output file name to `<name>` when no output name was given on the command line. A special case for Devpac-compatibility is when `<name>` starts with a `'.'` and an output name was already given. Then the current output name gets `<name>` appended as an extension. When an extension already exists, then it is replaced.

- page** Start a new page in the listing file (not implemented). Make sure to start a new page when the maximum page length is reached.
- plen <len>**
 Set the page length for a listing file to <len> lines. Currently ignored.
- printt <string>[,<string>...]**
 Prints <string> to stdout. Every additional string into a new line. Quotes are optional.
- printv <expression>[,<expression>...]**
 Evaluate <expression> and print it to stdout out in hexadecimal, decimal, ASCII and binary format.
- public <symbol>[,<symbol>...]**
 Flag <symbol> as an external symbol, which means that <symbol> is visible to all modules in the linking process. It may be either defined or undefined.
- popsection**
 Restore the top section from the internal section-stack and activate it. Also refer to **pushsection**.
- pushsection**
 Pushes the current section onto an internal stack, where it may be restored from by the **popsection** directive.
- rem** The assembler will ignore everything from encountering the **rem** directive until an **erem** directive was found.
- rept <expression>**
 Repeats the assembly of the block between **rept** and **endr** <expression> number of times. <expression> should be positive. Negative values are regarded like 0. The internal symbol REPTN always holds the iteration counter of the inner repeat loop, starting with 0. REPTN is -1 outside of any repeat block.
- rorg <expression>[,<fill>]**
 Sets the program counter to an offset relative to the start of the current section, as defined by <expression>. The new program counter (section offset) must not be smaller than the current one. Any space will be padded by the optional <fill> value, or zero.
- <label> rs.<size> <expression>**
 Works like the **so** directive, with the only difference that the offset symbol is named **__RS**.
- rseven** Align the structure offset counter (**__RS**) to an even count.
- rsreset** Equivalent to **clrso**, but the symbol manipulated is **__RS**.
- rsset <expression>**
 Sets the structure offset counter (**__RS**) to <expression>. See **rs** directive.
- section <name>[,<sec_type>][,<mem_type>]**
 Starts a new section named <name> or reactivates an old one. <sec_type> defines the section type and may be **code**, **text** (same as **code**), **data** or **bss**. If

the selected output format does not support section names (like "aout", "tos" or "xfile"), then a missing `<sec_type>` argument makes vasm interpret the first argument, `<name>`, as section type instead. Otherwise a missing `<sec_type>` defaults to a `code` section with the given name. The optional `<mem_type>` has currently only a meaning for the hunk-format output module and defines a 32-bit memory attribute which specifies where to load the section. `<mem_type>` is either a numerical constant or one of the keywords `chip` (for Chip-RAM) or `fast` (for Fast-RAM). Optionally it is also possible to attach the suffix `_C`, `_F` or `_P` to the `<sec_type>` argument for defining the memory type.

`<symbol> set <expression>`

Create a new symbol with the name `<symbol>` and assign the value of `<expression>`. If `<symbol>` is already assigned, it will contain a new value from now on.

`setfo <expression>`

Sets the structure offset counter (`__FO`) to `<expression>`. See `fo` directive.

`setso <expression>`

Sets the structure offset counter (`__SO`) to `<expression>`. See `so` directive.

`showoffset [<text>]`

Print current section offset (or absolute address) to the console, preceded by the optional `<text>` (may use quotes). PhxAss compatibility. Do not use in new code.

`<label> so.<size> <expression>`

Assigns the current value of the structure offset counter to `<label>`. Afterwards the counter is incremented by the instruction's `<size>` multiplied by `<expression>`. Any valid M68k size extension is allowed for `<size>`: `b`, `w`, `l`, `q`, `s`, `d`, `x`, `p`. The offset counter can also be referenced directly under the name `__SO`.

`spc <lines>`

Output `<lines>` number of blank lines in the listing file. Currently without any effect.

`text` Equivalent to `section code,code`.

`t1l <name>`

PhxAss syntax. Equivalent to `idnt <name>`.

`<name> t1l`

Motorola syntax. Equivalent to `idnt <name>`.

`weak <symbol>[,<symbol>...]`

Flag `<symbol>` as a weak symbol, which means that `<symbol>` is visible to all modules in the linking process, but may be replaced by any global symbol with the same name. When a weak symbol remains undefined its value defaults to 0.

`xdef <symbol>[,<symbol>...]`

Flag `<symbol>` as a global symbol, which means that `<symbol>` is visible to all modules in the linking process. See also `public`.

`xref <symbol>[,<symbol>...]`

Flag `<symbol>` as externally defined, which means it has to be imported from another module into the linking process. See also `public`.

4.5 Known Problems

Some known problems of this module at the moment:

- `odd` directive wastes two bytes, when address is already odd.
- Some listing file directives have no effect.
- Macro parameter replacement is also done when a line is commented out. This is a problem for special codes which modify the internal state, like `\@@`, `\@!`, `\@?`, `\+`, `\-`.
- `echo`, `printt` and `printv` do not work when the source text doesn't contain any real code.

4.6 Error Messages

This module has the following error messages:

- 1001: mnemonic expected
- 1002: invalid extension
- 1003: no space before operands
- 1004: too many closing parentheses
- 1005: missing closing parentheses
- 1006: missing operand
- 1007: garbage at end of line
- 1008: syntax error
- 1009: invalid data operand
- 1010: `,` expected
- 1011: identifier expected
- 1012: directive has no effect
- 1013: unexpected "%s" without "%s"
- 1014: illegal section type
- 1015: macro id insert on empty stack
- 1016: illegal memory type
- 1017: macro id stack overflow
- 1018: macro id pull without matching push
- 1019: check comment
- 1020: invalid numeric expansion
- 1021: `inline` without `inline`
- 1022: missing `%c`
- 1023: maximum inline nesting depth exceeded (%d)
- 1024: skipping instruction in struct init

- 1025: last %d bytes of string constant have been cut
- 1026: conditional assembly for pass 1 is not really supported, assuming true
- 1027: conditional assembly for pass 2 is not really supported, assuming false
- 1028: modified memory attributes for section "%s"

5 Madmac Syntax Module

This chapter describes the madmac syntax module, which is compatible to the MadMac assembler syntax, written by Landon Dyer for Atari and improved later to support Jaguar and JRISC. It is mainly intended for Atari's 6502, 68000 and Jaguar systems.

5.1 Legal

This module is written in 2015-2021 by Frank Wille and is covered by the vasm copyright without modifications.

5.2 General Syntax

A statement may contain up to four fields which are identified by order of appearance and terminating characters. The general form is:

```
label:    operator    operand(s)    ; comment
```

Labels must not start at the first column, as they are identified by the mandatory terminating colon (:) character. A double colon (::) automatically makes the label externally visible.

Labels preceded by '.' have local scope and are only valid between two global labels.

Equate directives, starting in the operator field, have a symbol without terminating colon in the first field, left of the operator. The equals-character (=) can be used as an alias for equ. A double-equals (==) automatically makes the symbol externally visible.

```
symbol    equate     expression    ; comment
```

Identifiers, like symbols or labels, may start with any upper- or lower-case character, a dot (.), question-mark (?) or underscore (_). The remaining characters may be any alphanumeric character, a dollar-sign (\$), question-mark (?) or underscore (_).

The operands are separated from the operator by whitespace. Multiple operands are separated by comma (,).

Comments are introduced by the comment character ;. The asterisk (*) can be used at the first column to start a comment. The rest of the line will be ignored.

In expressions, numbers starting with \$ are hexadecimal (e.g. \$fb2c). % introduces binary numbers (e.g. %1100101). Numbers starting with @ are assumed to be octal numbers, e.g. @237. All other numbers starting with a digit are decimal, e.g. 1239.

NOTE: Unlike the original Madmac assembler all expressions are evaluated following the usual mathematical operator priorities.

C-like escape characters are supported in strings.

5.3 Directives

The following directives are supported by this syntax module (if the CPU- and output-module allow it). Note that all directives, besides the equals-character, may be optionally preceded by a dot (.).

```
<symbol> = <expression>
```

Equivalent to <symbol> equ <expression>.

- <symbol> == <expression>**
 Equivalent to **<symbol> equ <expression>**, but declare **<symbol>** as externally visible.
- abs [<expression>]**
 Equivalent to **offset** for compatibility with older Madmac versions. Note that **abs** is not available for the jagrisc cpu backend as it conflicts with an instruction name.
- assert <expression>[,<expression>...]**
 Assert that all conditions are true (non-zero), otherwise issue a warning.
- bss**
 The following data (space definitions) are going into the BSS section. The BSS section cannot contain any initialized data.
- data**
 The following data are going into the data section, which usually contains pre-initialized data and no executable code.
- dc <exp1>[,<exp2>...]**
 Equivalent to **dc.w**.
- dc.b <exp1>[,<exp2>,<string1>,<string2>...]**
 Assign the integer or string constant operands into successive bytes of memory in the current section. Any combination of integer and character string constant operands is permitted.
- dc.i <exp1>[,<exp2>...]**
 Assign the values of the operands into successive 32-bit words of memory in the current section. In contrast to **dc.l** the high and low half-words will be swapped as with the Jaguar-RISC **movei** instruction.
- dc.l <exp1>[,<exp2>...]**
 Assign the values of the operands into successive 32-bit words of memory in the current section.
- dc.w <exp1>[,<exp2>...]**
 Assign the values of the operands into successive 16-bit words of memory in the current section.
- dcb**
 Equivalent to **dcb.w**.
- dcb.b <exp>[,<fill>]**
 Insert **<exp>** zero or **<fill>** bytes into the current section.
- dcb.l <exp>[,<fill>]**
 Insert **<exp>** zero or **<fill>** 32-bit words into the current section.
- dcb.w <exp>[,<fill>]**
 Insert **<exp>** zero or **<fill>** 16-bit words into the current section.
- dphrase**
 Align the program counter to the next integral double phrase boundary (16 bytes).
- ds <exp>**
 Equivalent to **dcb.w <exp>,0**.
- ds.b <exp>**
 Equivalent to **dcb.b <exp>,0**.

<code>ds.l <exp></code>	Equivalent to <code>dcbl <exp>,0</code> .
<code>ds.w <exp></code>	Equivalent to <code>dcblw <exp>,0</code> .
<code>else</code>	Else-part of a conditional-assembly block. Refer to 'if'.
<code>end</code>	End the assembly of the current file. Parsing of an include file is terminated here and assembling of the parent source commences. It also works to break the current conditional block, repetition or macro.
<code>endif</code>	Ends a block of conditional assembly.
<code>endm</code>	Ends a macro definition.
<code>endr</code>	Ends a repetition block.
<code><symbol> equ <expression></code>	Define a new program symbol with the name <symbol> and assign to it the value of <expression>. Defining <symbol> twice will cause an error.
<code>even</code>	Align the program counter to an even value, by inserting a zero-byte when it is odd.
<code>exitm</code>	Exit the current macro (proceed to <code>endm</code>) at this point and continue assembling the parent context. Note that this directive also resets the level of conditional assembly to a state before the macro was invoked (which means that it works as a 'break' command on all new <code>if</code> directives).
<code>extern <symbol>[,<symbol>...]</code>	Declare the given symbols as externally defined. Internally there is no difference to <code>globl</code> , as both declare the symbols, no matter if defined or not, as externally visible.
<code>globl <symbol>[,<symbol>...]</code>	Declare the given symbols as externally visible in the object file for the linker. Note that you can have the same effect by using a double-colon (:) on labels or a double-equal (==) on equate-symbols.
<code>if <expression></code>	Start of block of conditional assembly. If <expression> is true, the block between 'if' and the matching 'endif' or 'else' will be assembled. When false, ignore all lines until an 'else' or 'endif' directive is encountered. It is possible to leave such a block early from within an include file (with <code>end</code>) or a macro (with <code>endm</code>).
<code>iif <expression>, <statement></code>	A single-line conditional assembly. The <statement> will be parsed when <expression> evaluates to true (non-zero). <statement> may be a normal source line, including labels, operators and operands.
<code>incbin "<file>"</code>	Inserts the binary contents of <file> into the object code at this position.

include "<file>"
 Include source text of <file> at this position.

list
 The following lines will appear in the listing file, if it was requested.

long
 Align the program counter to the next integral longword boundary (4 bytes), by inserting as many zero-bytes as needed.

macro <name> [<argname>[,<argname>...]]
 Defines a macro which can be referenced by <name> (case-sensitive). The macro definition is terminated by an **endm** directive and may be exited by **exitm**. When calling a macro you may pass up to 64 arguments, separated by comma. The first ten arguments are referenced within the macro context as \1 to \9 and \0 for the tenth. Optionally you can specify a list of argument names, which are referenced with a leading backslash character (\) within the macro. The special code \~ inserts a unique id, useful for defining labels. \# is replaced by the number of arguments. \! writes the the size-qualifier (M68k) including the dot. \?argname expands to 1 when the named argument is specified and non-empty, otherwise it expands to 0. It is also allowed to enclose argument names in curly braces, which is useful in situations where the argument name is followed by another valid identifier character.

macundef <name>[,<name>...]
 Undefine one or more already defined macros, making them unknown for the following source to assemble.

nlist
 The following lines will not be visible in a listing file.

nolist
 The following lines will not be visible in a listing file.

offset [<expression>]
 Switches to a special offset-section. The contents of such a section is not included in the output. Their labels may be referenced as absolute offset symbols. Can be used to define structure offsets. The optional <expression> gives the start offset for this section. Defaults to zero when omitted. <expression> must evaluate as a constant!

org <expression>
 Sets the base address for the subsequent code and switch into absolute mode. Such a block is terminated by any section directive or by **.68000**.

phrase
 Align the program counter to the next integral phrase boundary (8 bytes).

print <expression>[,<expression>...]
 Prints strings and formatted expressions to the assembler's console. <expression> is either a string in quotes or an expression, which is optionally preceded by special format flags:
 Several flags can be used to format the output of expressions. The default is a 16-bit signed decimal.

/x	hexadecimal
/d	signed decimal

/u unsigned decimal
 /w 16-bit word
 /l 32-bit longword

For example:

```
.print "Value: ", /d/l xyz
```

qphrase Align the program counter to the next integral quad phrase boundary (32 bytes).

rept <expression>

The block between **rept** and **endr** will be repeated <expression> times, which has to be positive.

<symbol> set <expression>

Create a new symbol with the name <symbol> and assign the value of <expression>. If <symbol> is already assigned, it will contain a new value from now on.

text The following code and data is going into the text section, which usually is the first program section, containing the executable code.

5.4 Known Problems

Some known problems of this module at the moment:

- Not all Madmac, smac and extended Jaguar-Madmac directives are supported.
- Expressions are not evaluated left-to-right, but mathematically correct.
- Square-brackets ([]) are currently not supported to prioritize terms, as an alternative for parentheses.
- Functions (^^func) are currently not supported.

5.5 Error Messages

This module has the following error messages:

- 1001: malformed immediate-if
- 1003: cannot export local symbol
- 1004: no space before operands
- 1005: too many closing parentheses
- 1006: missing closing parentheses
- 1007: missing operand
- 1008: garbage at end of line
- 1009: unknown print format flag '%c'
- 1010: invalid data operand
- 1011: print format corrupted
- 1012: identifier expected
- 1014: unexpected "%s" without "%s"

6 Oldstyle Syntax Module

This chapter describes the oldstyle syntax module suitable for some 8-bit CPUs (6502, 680x, 68HC1x, Z80, etc.), which is available with the extension `oldstyle`.

6.1 Legal

This module is written in 2002-2023 by Frank Wille and is covered by the vasm copyright without modifications.

6.2 Additional options for this module

This syntax module provides the following additional options:

- `-autoexp` Automatically export all non-local symbols, making them visible to other modules during linking.
- `-ast` Allow the asterisk (*) for starting comments in the first column. This disables the possibility to set the code origin with `*=addr` in the first column.
- `-dotdir` Directives have to be preceded by a dot (.).
- `-i` Ignore everything after a blank in the operand field and treat it as a comment. This option is only available when the backend does not separate its operands with blanks as well.
- `-ldots` Allow dots (.) within all identifiers.
- `-noc` Disable C-style constant prefixes.
- `-noi` Disable intel-style constant suffixes.
- `-sect` Enables the additional section directives `text`, `data` and `bss`, which switch to their respective section type. The original `text` directive for creating string-constants and the `data` directive for creating byte-constants are no longer available. But there are still other directives for the same purpose.

6.3 General Syntax

Labels always start at the first column and may be terminated by a colon (:), but don't need to. In the latter case the mnemonic has to be separated from the label by whitespace (not required in any case, e.g. with =).

Local labels are preceded by `'.'` or terminated by `'$'`. For the rest, any alphanumeric character including `'_'` is allowed. Local labels are valid between two global label definitions.

It is allowed, but not recommended, to refer to any local symbol starting with `'.'` in the source, by preceding its name with the name of the last previously defined global symbol: `global_name.local_name`.

Anonymous labels are supported by defining them with a single `':'` at the beginning of a line. They may be referenced by `':'` followed directly by one or more `'+'` or `'-'` signs. A `+` selects the first anonymous label following the point of reference. A `++` select the second

anonymous label in that direction, and so on. A - selects the first anonymous label before the point of reference. Example:

```
      :      jmp      :-      ;infinite loop
```

The option `-ldots` allows dots (.) within labels and other identifiers, but disables the above mentioned feature.

The operands are separated from the mnemonic by whitespace. Multiple operands are separated by comma (,).

Make sure that you don't define a label on the same line as a directive for conditional assembly (if, else, endif)! This is not supported.

Some CPU backends may support multiple statements (directives or mnemonics) per line, separated by a special character (e.g. `:` for Z80).

Comments are introduced by the comment character (`;`), or the first blank following the operand field when option `-i` was given. The rest of the line will be ignored.

Example:

```
mylabel instr op1,op2 ;comment
```

In expressions, numbers starting with `$` are hexadecimal (e.g. `$fb2c`). For Z80 also `&` may be used as a hexadecimal prefix, but make sure to avoid conflicts with the and-operator (either by using parentheses or blanks). `%` introduces binary numbers (e.g. `%1100101`). Numbers starting with `@` are assumed to be octal numbers, e.g. `@237` (except for Z80, where it means binary). A special case is a digit followed by a `#`, which can be used to define an arbitrary base between 2 and 9 (e.g. `4#3012`). Intel-style constant suffixes are supported: `h` for hexadecimal, `d` for decimal, `o` or `q` for octal and `b` for binary. Hexadecimal intel-style constants must start with a digit (prepend 0, when required). Also C-style prefixes are supported for hexadecimal (`0x`) and binary (`0b`). All other numbers starting with a digit are decimal, e.g. `1239`.

6.4 Directives

The following directives are supported by this syntax module (if the CPU- and output-module allow it):

`<symbol> = <expression>`

Equivalent to `<symbol> equ <expression>`.

`abyte <modifier>,<exp1>[,<exp2>,"<string1>"...]`

Write the integer or string constants into successive bytes of memory in the current section while modifying each expression (and string-character) by the modifier expression. When the modifier contains the special `._` symbol, then it is a placeholder for any expression from the line. Otherwise the modifier will be just added to each element. Any combination of integer and character string constants is permitted.

`addr <exp1>[,<exp2>...]`

Assign the values of the operands into successive words of memory in the current section, using the target's endianness and address size.

align <bitcount>
 Insert as much zero bytes as required to reach an address where <bit_count> low order bits are zero. For example **align 2** would make an alignment to the next 32-bit boundary.

asc <exp1>[,<exp2>,"<string1>"...]
 Equivalent to **byte** <exp1>[,<exp2>,"<string1>"...].

ascii <exp1>[,<exp2>,"<string1>"...]
 See **defm**.

asciiz "<string1>"[, "<string2>"...]
 See **string**.

assert <expression>[,<message>]
 Display an error with the optional <message> when the expression is false.

binary <file>
 Inserts the binary contents of <file> into the object code at this position.

blk <exp>[,<fill>]
 Insert <exp> zero or <fill> bytes into the current section.

blkw <exp>[,<fill>]
 Insert <exp> zero or <fill> 16-bit words into the current section, using the endianness of the target CPU.

bss With option **-sect**: switches to a bss section with attributes "aurw".

bsz <exp>[,<fill>]
 Equivalent to **blk** <exp>[,<fill>].

byt <exp1>[,<exp2>,"<string1>"...]
 Assign the integer or string constant operands into successive bytes of memory in the current section. Any combination of integer and character string constant operands is permitted. Without any operands the program counter is just incremented by one.

byte <exp1>[,<exp2>,"<string1>"...]
 Equivalent to **byt** <exp1>[,<exp2>,"<string1>"...].

data <exp1>[,<exp2>,"<string1>"...]
 Equivalent to **byt** <exp1>[,<exp2>,"<string1>"...]. (Not available with option **-sect**.)

data With option **-sect**: switches to a data section with attributes "adrw".

db <exp1>[,<exp2>,"<string1>"...]
 Equivalent to **byt** <exp1>[,<exp2>,"<string1>"...].

dc <exp>[,<fill>]
 Equivalent to **blk** <exp>[,<fill>].

defb <exp1>[,<exp2>,"<string1>"...]
 Equivalent to **byte** <exp1>[,<exp2>,"<string1>"...].

defc <symbol> = <expression>
 Define a new program symbol with the name <symbol> and assign to it the value of <expression>. Defining <symbol> twice will cause an error.

defl <exp1>[,<exp2>...]
 Assign the values of the operands into successive 32-bit integers of memory in the current section, using the endianness of the target CPU.

defp <exp1>[,<exp2>...]
 Assign the values of the operands into successive 24-bit integers of memory in the current section, using the endianness of the target CPU.

defm "string"
 Equivalent to **text** "string".

defw <exp1>[,<exp2>...]
 Equivalent to **word** <exp1>[,<exp2>...].

dfb <exp1>[,<exp2>,"<string1>"...]
 Equivalent to **byte** <exp1>[,<exp2>,"<string1>"...].

dfw <exp1>[,<exp2>...]
 Equivalent to **word** <exp1>[,<exp2>...].

defs <exp>[,<fill>]
 Equivalent to **blk** <exp>[,<fill>].

dend
 Ends an offset-section started by **dsect** and restores the previously active section.

dephase
 Equivalent to **rend**.

ds <exp>[,<fill>]
 Equivalent to **blk** <exp>[,<fill>].

dsb <exp>[,<fill>]
 Equivalent to **blk** <exp>[,<fill>].

dsect
 Starts an 'offset-section' (the original directive in ADE was called 'dummy-section') which does not generate any code in the output file. Its only purpose is to define absolute labels. Within a **dsect** block you may use **org** directives to set a new offset, which defaults to zero for the first **dsect** otherwise. Following **dsect** sections continue with the last offset from the former. Such an offset-section block is closed by the **dend** directive, which restores the previous 'real' section.

dsw <exp>[,<fill>]
 Equivalent to **blkw** <exp>[,<fill>].

dw <exp1>[,<exp2>...]
 Equivalent to **word** <exp1>[,<exp2>...].

end
 Assembly will terminate behind this line.

endif
 Ends a section of conditional assembly.

el
 Equivalent to **else**.

`else` Assemble the following lines when the previous `if`-condition was false.
`ei` Equivalent to `endif`. (Not available for Z80 CPU)
`inline` End a block of isolated local labels, started by `inline`.
`endm` Ends a macro definition.
`endmac` Ends a macro definition.
`endmacro` Ends a macro definition.
`endr` Ends a repetition block.
`endrep` Ends a repetition block.
`endrepeat`
 Ends a repetition block.
`endstruct`
 Ends a structure definition.
`endstructure`
 Ends a structure definition.
`<symbol> eq <expression>`
 Equivalent to `<symbol> equ <expression>`.
`<symbol> equ <expression>`
 Define a new program symbol with the name `<symbol>` and assign to it the
 value of `<expression>`. Defining `<symbol>` twice will cause an error.
`extern <symbol>[,<symbol>...]`
 See `global`.
`even` Aligns to an even address. Equivalent to `align 1`.
`fail <message>`
 Show an error message including the `<message>` string. Do not generate an
 output file.
`fi` Equivalent to `endif`.
`fill <exp>`
 Equivalent to `blk <exp>,0`.
`fcb <exp1>[,<exp2>,"<string1>"...]`
 Equivalent to `byte <exp1>[,<exp2>,"<string1>"...]`.
`fcc "<string>"`
 Equivalent to `text`.
`fcs "<string>"`
 Works like `text` and `fcc`, but additionally sets the most significant bit of the
 last byte. This can be used as a string terminator on some systems.
`fdb <exp1>[,<exp2>,"<string1>"...]`
 Equivalent to `word <exp1>[,<exp2>...]`.

`global <symbol>[,<symbol>...]`

Flag <symbol> as an external symbol, which means that <symbol> is visible to all modules in the linking process. It may be either defined or undefined.

`if <expression>`

Conditionally assemble the following lines if <expression> is non-zero.

`ifdef <symbol>`

Conditionally assemble the following lines if <symbol> is defined.

`ifndef <symbol>`

Conditionally assemble the following lines if <symbol> is undefined.

`ifd <symbol>`

Conditionally assemble the following lines if <symbol> is defined.

`ifnd <symbol>`

Conditionally assemble the following lines if <symbol> is undefined.

`ifeq <expression>`

Conditionally assemble the following lines if <expression> is zero.

`ifne <expression>`

Conditionally assemble the following lines if <expression> is non-zero.

`ifgt <expression>`

Conditionally assemble the following lines if <expression> is greater than zero.

`ifge <expression>`

Conditionally assemble the following lines if <expression> is greater than zero or equal.

`iflt <expression>`

Conditionally assemble the following lines if <expression> is less than zero.

`ifle <expression>`

Conditionally assemble the following lines if <expression> is less than zero or equal.

`ifused <symbol>`

Conditionally assemble the following lines if <symbol> has been previously referenced in an expression or in a parameter of an opcode. Issue a warning, when <symbol> is already defined. Note that `ifused` does not work, when the symbol has only been used in the following lines of the source.

`incbin <file>[,<offset>[,<nbytes>]]`

Inserts the binary contents of <file> into the object code at this position. When <offset> is specified, then the given number of bytes will be skipped at the beginning of the file. The optional <nbytes> argument specifies the maximum number of bytes to be read from that file.

`incdir <path>`

Add another path to search for include files to the list of known paths. Paths defined with `-I` on the command line are searched first.

include <file>
 Include source text of <file> at this position.

inline Local labels in the following block are isolated from previous local labels and those after **einline**.

mac <name>
 Equivalent to **macro** <name>.

list The following lines will appear in the listing file, if it was requested.

local <symbol>[,<symbol>...]
 Flag <symbol> as a local symbol, which means that <symbol> is local for the current file and invisible to other modules in the linking process.

macro <name>[,<argname>...]
 Defines a macro which can be referenced by <name>. The <name> may also appear at the left side of the **macro** directive, starting on the first column. The macro definition is closed by an **endm** directive. When calling a macro you may pass up to 9 arguments, separated by comma. These arguments are referenced within the macro context as \1 to \9, or optionally by named arguments, which you have to specify in the operand. Argument \0 is set to the macro's first qualifier (mnemonic extension), when given. The special argument \@ inserts an underscore followed by a six-digit unique id, useful for defining labels. \() may be used as a separator between the name of a macro argument and the subsequent text. \<symbolname> inserts the current decimal value of the absolute symbol **symbolname**.

mdat <file>
 Equivalent to **incbin** <file>.

needs <expression>
 Equivalent to **symdepend** <expression>.

nolist The following lines will not be visible in a listing file.

org [#]<expression>
 Sets the base address for the subsequent code. This is equivalent to ***=<expression>**. An optional # is supported for compatibility reasons.

phase <expression>
 Equivalent to **rorg** <expression>.

repeat <expression>
 Equivalent to **rept** <expression>.

rept <expression>
 Repeats the assembly of the block between **rept** and **endr** <expression> number of times. <expression> has to be positive.

reserve <exp>
 Equivalent to **blk** <exp>,0.

rend Ends a **rorg** block of label relocation. Following labels will be based on **org** again.

rmb <exp>[,<fill>]

Equivalent to **blk** <exp>[,<fill>]. (Not available for 6502 CPU.)

roffs <expression>

Sets the program counter <expression> bytes behind the start of the current section. The new program counter must not be smaller than the current one. The space will be padded with zeros.

rorg <expression>

Relocate all labels between **rorg** and **rend** based on the new origin from <expression>.

section <name>[, "<attributes>"]

Starts a new section named <name> or reactivate an old one. If attributes are given for an already existing section, they must match exactly. The section's name will also be defined as a new symbol, which represents the section's start address. The "<attributes>" string may consist of the following characters:

Section Contents:

c	section has code
d	section has initialized data
u	section has uninitialized data
i	section has directives (info section)
n	section can be discarded
R	remove section at link time
a	section is allocated in memory

Section Protection:

r	section is readable
w	section is writable
x	section is executable
s	section is shareable

When attributes are missing they are automatically set for the section names **text**, **data**, **rodata**, **bss**, **.text**, **.data**, **.rodata** and **.bss**. Otherwise they default to "acrwX".

<symbol> **set** <expression>

Create a new symbol with the name <symbol> and assign the value of <expression>. If <symbol> is already assigned, it will contain a new value from now on.

spc <exp> Equivalent to **blk** <exp>,0.

str "<string1>"[, "<string2>"...]

Like **text**, but adds a terminating carriage return (ASCII code 13).

string "<string1>"[, "<string2>"...]

Like **text**, but adds a terminating zero-byte.

struct <name>

Defines a structure which can be referenced by <name>. Labels within a structure definition can be used as field offsets. They will be defined as local labels of <name> and can be referenced through <name>.<label>. All directives are allowed, but instructions will be ignored when such a structure is used. Data definitions can be used as default values when the structure is used as initializer. The structure name, <name>, is defined as a global symbol with the structure's size. A structure definition is ended by **endstruct**.

structure <name>

Equivalent to **struct** <name>.

symdepend <expression>

Declare the current section being dependent on an externally defined symbol from <expression>. In object file formats which support it, this will generate an external symbol reference without any actual relocation being performed (R_NONE in ELF).

text "<string>"

Puts a single string constant into successive bytes of memory of the current section. The string delimiters may be any printable ASCII character. (Not available with option **-sect**.)

text

With option **-sect**: switches to a code section with attributes "acrx".

weak <symbol>[, <symbol>...]

Flag <symbol> as a weak symbol, which means that <symbol> is visible to all modules in the linking process and may be replaced by any global symbol with the same name. When a weak symbol remains undefined its value defaults to 0.

wor <exp1>[, <exp2>...]

Assign the values of the operands into successive 16-bit words of memory in the current section, using the endianness of the target CPU. Without any operand just the program counter is incremented by two.

wrd <exp1>[, <exp2>...]

Equivalent to **wor** <exp1>[, <exp2>...].

word <exp1>[, <exp2>...]

Equivalent to **wor** <exp1>[, <exp2>...].

xdef <symbol>[, <symbol>...]

See **global**.

xlib <symbol>[, <symbol>...]

See **global**.

xref <symbol>[, <symbol>...]

See **global**.

`zmb <exp>[,<fill>]`
 Equivalent to `blk <exp>[,<fill>]`.

6.5 Structures

The oldstyle syntax is able to manage structures. Structures can be defined in two ways:

```
mylabel struct[ure]
    <fields>
endstruct[ure]
```

or:

```
struct[ure] mylabel
    <fields>
endstruct[ure]
```

Any directive is allowed to define the structure fields. Labels can be used to define offsets into the structure. The initialized data is used as default value, whenever no value is given for a field when the structure is referenced.

Some examples of structure declarations:

```
struct point
x    db 4
y    db 5
z    db 6
endstruct
```

This will create the following labels:

```
point.x ; 0    offsets
point.y ; 1
point.z ; 2
point   ; 3    size of the structure
```

The structure can be used by optionally redefining the field values:

```
point1 point
point2 point 1, 2, 3
point3 point ,,4
```

is equivalent to

```
point1
    db 4
    db 5
    db 6

point2
    db 1
    db 2
    db 3

point3
    db 4
    db 5
    db 4
```

6.6 Known Problems

Some known problems of this module at the moment:

- Addresses assigned to `org` or to the current pc symbol `'*`' (on the Z80 the pc symbol is `'$'`) must be constant.
- Expressions in an `if` directive must be constant.

6.7 Error Messages

This module has the following error messages:

- 1001: syntax error
- 1002: invalid extension
- 1003: no space before operands
- 1004: too many closing parentheses
- 1005: missing closing parentheses
- 1006: missing operand
- 1007: garbage at end of line
- 1008: `%c` expected
- 1009: invalid data operand
- 1010: `,` expected
- 1011: identifier expected
- 1012: illegal escape sequence `%c`
- 1013: unexpected `"%s"` without `"%s"`
- 1014: `dsect` already active
- 1015: `dend` without `dsect`
- 1016: missing `dend`
- 1018: maximum inline nesting depth exceeded (`%d`)
- 1017: `inline` without `inline`
- 1021: cannot open binary file `"%s"`
- 1023: alignment too big
- 1024: label `<%s>` has already been defined
- 1025: skipping instruction in struct init
- 1026: last `%d` bytes of string constant have been cut

7 Test output module

This chapter describes the test output module which can be selected with the `-Ftest` option.

7.1 Legal

This module is written in 2002 by Volker Barthelmann and is covered by the vasm copyright without modifications.

7.2 Additional options for this module

This output module provides no additional options.

7.3 General

This output module outputs a textual description of the contents of all sections. It is mainly intended for debugging.

7.4 Restrictions

None.

7.5 Known Problems

Some known problems of this module at the moment:

- None.

7.6 Error Messages

This module has the following error messages:

- None.

8 ELF output module

This chapter describes the ELF output module which can be selected with the `-Felf` option.

8.1 Legal

This module is written in 2002-2016 by Frank Wille and is covered by the vasm copyright without modifications.

8.2 Additional options for this module

`-keepempty`

Do not delete empty sections without any symbol definition.

8.3 General

This output module outputs the **ELF** (Executable and Linkable Format) format, which is a portable object file format and works for a variety of 32- and 64-bit operating systems.

8.4 Restrictions

The ELF output format, as implemented in vasm, currently supports the following architectures:

- PowerPC
- M68k
- ARM
- i386
- x86_64
- Jaguar RISC

The supported relocation types depend on the selected architecture.

8.5 Known Problems

Some known problems of this module at the moment:

- None.

8.6 Error Messages

This module has the following error messages:

- 3002: output module doesn't support cpu <name>
- 3003: write error
- 3005: reloc type <m>, size <n>, mask <mask> (symbol <sym> + <offset>) not supported
- 3006: reloc type <n> not supported
- 3010: section <%s>: alignment padding (%lu) not a multiple of %lu at 0x%llx

9 a.out output module

This chapter describes the a.out output module which can be selected with the `-Faout` option.

9.1 Legal

This module is written in 2008-2016,2020,2021 by Frank Wille and is covered by the vasm copyright without modifications.

9.2 Additional options for this module

`-mid=<machine id>`

Sets the MID field of the a.out header to the specified value. The MID defaults to 2 (Sun020 big-endian) for M68k and to 100 (PC386 little-endian) for x86.

9.3 General

This output module emits the **a.out** (assembler output) format, which is an older 32-bit format for Unix-like operating systems, originally invented by AT&T.

9.4 Restrictions

The **a.out** output format, as implemented in vasm, currently supports the following architectures:

- M68k
- i386

The following standard relocations are supported by default:

- absolute, 8, 16, 32 bits
- pc-relative, 8, 16, 32 bits
- base-relative

Standard relocation table entries occupy 8 bytes and don't include an addend, so they are not suitable for most RISC CPUs. The extended relocations format occupies 12 bytes and also allows more relocation types.

9.5 Known Problems

Some known problems of this module at the moment:

- The extended relocation format is not supported.

9.6 Error Messages

This module has the following error messages:

- 3004: section attributes <attr> not supported
- 3008: output module doesn't allow multiple sections of the same type
- 3010: section <%s>: alignment padding (%lu) not a multiple of %lu at 0x%llx

10 TOS output module

This chapter describes the TOS output module, which can be selected with option **-Ftos** to generate Atari TOS executable files, or with option **-Fdri** to generate DRI-format object files.

10.1 Legal

This module is written in 2009-2016,2020,2021,2023 by Frank Wille and is covered by the vasm copyright without modifications.

10.2 Additional options for this module

-szbx Use the SozobonX extension, which allows symbol names with unlimited length in DRI objects and executables. Overrides the HiSoft extension.

-stdsymbols
 Do not write HiSoft extended symbol names. Cut at 8 characters.

These options are valid for the **tos** module only:

-monst Write Devpac "MonST"-compatible symbols.

-tos-flags=<flags>
 Sets the flags field in the TOS file header. Defaults to 0. Overwrites a TOS flags definition in the assembler source.

10.3 General

-Ftos The TOS executable file format is used on Atari 16/32-bit computers with 68000 up to 68060 CPU running any TOS, MiNT or any compatible operating system. The symbol table is in DRI format and may use HiSoft (default) or SozobonX extended symbol names.

-Fdri The object file format defined by Digital Research for Atari M68k systems.

10.4 Restrictions

- These file formats only support a single Text (code), Data and BSS section.
- For **tos** all symbols must be defined, otherwise the generation of the executable fails. Unknown symbols are listed by vasm.
- The only relocations allowed in **tos** are 32-bit absolute. For **dri** all 16- and 32-bit absolute and PC-relative relocations are supported. 16-bit base-relative appears as a 16-bit absolute symbol reference.
- The maximum symbol length is 8 characters only. The **tos** format increases the maximum length to 22 by using an extension created by HiSoft, unless forbidden by **-stdsymbols**. With **-szbx** you may enable the SozobonX extension for unlimited length - but you need a linker which supports that format.
- Symbol references in **dri** object files are limited to a maximum of 8192 symbols.

All these restrictions are defined by the file format itself.

10.5 Known Problems

Some known problems of this module at the moment:

- None.

10.6 Error Messages

This module has the following error messages:

- 3004: section attributes <attr> not supported
- 3005: reloc type %d, size %d, mask 0x%lx (symbol %s + 0x%lx) not supported
- 3006: reloc type %d not supported
- 3007: undefined symbol <%s>
- 3008: output module doesn't allow multiple sections of the same type
- 3010: section <%s>: alignment padding (%lu) not a multiple of %lu at 0x%llx
- 3011: weak symbol <%s> not supported by output format, treating as global
- 3020: too many symbols for selected output file format

11 GST output module

This chapter describes the `gst` output module which can be selected with the `-Fgst` option.

11.1 Legal

This module is written in 2023 by Frank Wille and is covered by the `vasm` copyright without modifications.

11.2 Additional options for this module

None.

11.3 General

This module outputs the GST object file format by GST Software, which was used by several development tools on the Atari M68k computers. For example by the GST assembler and Devpac.

11.4 Restrictions

- Although there can be multiple sections, they don't have a type.
- Maximum size of section and symbol names is 255 characters.
- Only absolute, pc-relative and common-symbol relocations are supported at the moment.
- Possible relocation sizes are 8, 16 and 32 bits.

11.5 Known Problems

Some known problems of this module at the moment:

- Needs testing.
- Missing support for base-relative relocations.

11.6 Error Messages

This module has the following error messages:

- 3002: output module doesn't support cpu %s
- 3011: weak symbol <%s> not supported by output format, treating as global
- 3013: reloc type %d, mask 0x%lx to symbol %s + 0x%lx does not fit into %u bits

12 Amiga output module

This chapter describes the AmigaOS hunk-format output module which can be selected with the `-Fhunk` option to generate objects and with the `-Fhunkexe` option to generate executable files.

12.1 Legal

This module is written in 2002-2022 by Frank Wille and is covered by the vasm copyright without modifications.

12.2 Additional options for this module

`-hunkpad=<code>`

Sets a two-byte code used for aligning a code hunk to the next 32-bit border. Defaults to 0x4e71 for M68k code sections, to allow linking of functions which extend over two object files. Otherwise it defaults to zero.

`-keepempty`

Do not delete empty sections without any symbol definition.

`-kick1hunks`

Use only those hunk types and external reference types which have been valid at the time of Kickstart 1.x for compatibility with old assembler sources and old linkers. For example: no longer differentiate between absolute and relative references. In executables it will prevent the assembler from using 16-bit relocation offsets in hunks and rejects 32-bit PC-relative relocations.

`-linedebug`

Automatically generate an SAS/C-compatible LINE DEBUG hunk for the input source. Overrides any line debugging directives from the source text.

These options are valid for the **hunkexe** module only:

`-databss` Try to shorten sections in the output file by removing zero words without relocation from the end. This technique is only supported by AmigaOS 2.0 and higher.

12.3 General

This output module outputs the **hunk** object (standard for M68k and extended for PowerPC) and **hunkexe** executable format, which is a proprietary file format used by AmigaOS and WarpOS.

The **hunkexe** module will generate directly executable files, without the need for another linker run. But you have to make sure that there are no undefined symbols, common symbols, or unusual relocations (e.g. small data) left.

It is allowed to define sections with the same name but different attributes. They will be regarded as different entities.

12.4 Restrictions

The **hunk**/**hunkexe** output format is only intended for **M68k** and **PowerPC** cpu modules and will abort when used otherwise.

The **hunk** module supports the following relocation types:

- absolute, 32-bit
- absolute, 16-bit
- absolute, 8-bit
- relative, 8-bit
- relative, 14-bit (mask 0xffff) for PPC branch instructions.
- relative, 16-bit
- relative, 24-bit (mask 0x3ffff) for PPC branch instructions.
- relative, 32-bit
- base-relative, 16-bit
- common symbols are supported as 32-bit absolute and relative references

The **hunkexe** module supports absolute 32-bit relocations only.

12.5 Known Problems

Some known problems of this module at the moment:

- The **hunkexe** module won't process common symbols and allocate them in a **BSS** section. Use a real linker for that.

12.6 Error Messages

This module has the following error messages:

- 3001: multiple sections not supported by this format
- 3002: output module doesn't support cpu <name>
- 3003: write error
- 3004: section attributes <attr> not supported
- 3005: reloc type <m>, size <n>, mask <mask> (symbol <sym> + <offset>) not supported
- 3006: reloc type <n> not supported
- 3009: undefined symbol <%s> at %s+0x%lx, reloc type %d
- 3010: section <%s>: alignment padding (%lu) not a multiple of %lu at 0x%llx
- 3011: weak symbol <%s> not supported by output format, treating as global
- 3014: data definition following a databss space directive
- 3016: absolute file path exceeds maximum size of %d characters
- 3017: converting NONE relocation <%s> to 8-bit ABS with zero addend
- 3018: no additional space in section to convert NONE relocation <%s> to ABS
- 3019: section <%s>: kickstart 1.x cannot initialize bss sections >256k to zero

13 X68k output module

This chapter describes the Xfile output module which can be selected with the `-Fxfile` option.

13.1 Legal

This module is written in 2018,2020,2021 by Frank Wille and is covered by the vasm copyright without modifications.

13.2 Additional options for this module

None.

13.3 General

This module outputs the Xfile executable file format, which is used on Sharp X68000 16/32-bit computer with 68000 up to 68040 CPU.

13.4 Restrictions

- The source must not define more than one code, data and bss section each. More complex sources with `.rdata` or `.stack` sections require a linker.
- All symbols must be defined, otherwise the generation of the executable fails. Unknown symbols are listed by vasm.
- The only relocations allowed in this format are 32-bit absolute.

13.5 Known Problems

Some known problems of this module at the moment:

- None.

13.6 Error Messages

This module has the following error messages:

- 3004: section attributes <attr> not supported
- 3005: reloc type %d, size %d, mask 0x%lx (symbol %s + 0x%lx) not supported
- 3006: reloc type %d not supported
- 3007: undefined symbol <%s>
- 3008: output module doesn't allow multiple sections of the same type
- 3011: weak symbol <%s> not supported by output format, treating as global
- 3013: reloc type %d, mask 0x%lx to symbol %s + 0x%lx does not fit into %u bits

14 O65 output module

This chapter describes the O65 binary relocation format V1.3 for the 6502 family, as defined by Andre Fachat on 6502.org. Option `-Fo65` outputs object files suitable for another linker pass, while `-Fo65exe` outputs executable files for an O65 loader. The difference is just a flag which declares the file being an object, and vasm will make sure that the load-addresses of sections in an executable will be consecutive and do not overlay.

14.1 Legal

This module is written in 2021 by Frank Wille and is covered by the vasm copyright without modifications.

14.2 Additional options for this module

- `-bss=<addr>`
Sets a start address for the **bss** section.
- `-data=<addr>`
Sets a start address for the **data** section.
- `-fopts` Enable informational header options, generated by the assembler: file name, assembler name and version, creation date.
- `-foauthor=<name>`
Write author's name to the header options.
- `-foname=<name>`
Write file name to the header options. Overwrites the real file name, which would be set by `-fopts`.
- `-paged` Make the output file use paged alignment and simplified paged relocations.
- `-secalign=<align>`
Set minimum alignment for all sections as number of least significant bits which have to be zero. **align** may be 0, 1, 2, 8. The default behaviour is to use the maximum alignment given by the input sections.
- `-stack=<stacksize>`
Store required stack size in the header.
- `-text=<addr>`
Sets a start address for the **text** section.
- `-zero=<addr>`
Sets a start address for the **zero** (zero/direct page) section.

These options are valid for the `o65exe` module only:

- `-bsszero` Set a flag in the header which requests automatic clearing of the **bss** section.

14.3 General

This output module outputs the `o65` object file and `o65exe` executable file format for 6502-family processors and the 65816. The processor type is determined by the selected CPU of the active backend and stored in the header.

The `o65exe` module generates executable files for a `o65`-loader, which is present in some 6502 operating systems (e.g. Linux, SMOS, OS/A65). Unresolved symbols are allowed in `o65` object- and executable-files. In the latter case the `o65`-loader is responsible to resolve them. Common symbols, weak symbol and most relocation types, except absolute addresses, are not supported by `o65`.

The `o65` format recognizes four different sections by their attributes or name:

- text, sections which have executable code and/or are not writable (`acrx`).
- data, sections which have initialized data and may be read and written (`adrw`).
- bss, sections which have uninitialized data and may be read and written (`aurw`).
- zero, sections which have uninitialized data, may be read and written, and do not have the string "bss" anywhere in their name (`aurw`).

Up to two absolute sections (`ORG` directive) can be stored in the `text` and `data` slots, in the order of occurrence.

14.4 Restrictions

Currently the `o65/o65exe` output module is only intended to work with the 6502 cpu module and will abort when used otherwise.

It supports all relocation types defined by `o65`, which are:

- 0x20: absolute, 8-bit value or low-byte of 16-bit address
- 0x40: absolute, 8-bit high-byte of 16-bit address
- 0x80: absolute, 16-bit address
- 0xa0: absolute, 8-bit segment-byte of 24-bit address
- 0xc0: absolute, 24-bit address

Common or weak symbols are not supported.

14.5 Known Problems

Some known problems of this module at the moment:

- Needs a better way to set start addresses for the sections in the assembler.

14.6 Error Messages

This module has the following error messages:

- 3004: section attributes <attr> not supported
- 3008: output module doesn't allow multiple sections of the same type (%s)
- 3011: weak symbol <%s> not supported by output format, treating as global
- 3015: file option %d max size exceeded: %lu

15 vobj output module

This chapter describes the simple binary output module which can be selected with the `-Fvobj` option.

15.1 Legal

This module is written in 2002-2014 by Volker Barthelmann and is covered by the vasm copyright without modifications.

15.2 Additional options for this module

None.

15.3 General

This output module outputs the `vobj` object format, a simple portable proprietary object file format of `vasm`.

As this format is not yet fixed, it is not described here.

15.4 Restrictions

None.

15.5 Known Problems

Some known problems of this module at the moment:

- None.

15.6 Error Messages

This module has the following error messages:

- 3010: section `<%s>`: alignment padding (`%lu`) not a multiple of `%lu` at `0x%llx`

16 Simple binary output module

This chapter describes the simple binary output module which can be selected with the `-Fbin` option.

16.1 Legal

This module is written in 2002-2023 by Volker Barthelmann and Frank Wille and is covered by the vasm copyright without modifications.

16.2 Additional options for this module

`-apple-bin`

Writes an Apple DOS 3.3 binary file header preceding the output file, which consists of a 16-bit start/load address and a 16-bit file length in little-endian order.

`-atari-com`

Writes an Atari DOS COM header preceding the output file. It has a standard header (0xFFFF), which is followed by any number of sections. Each section starts with two little-endian words defining the address of the first and last byte in memory.

`-cbm-prg`

Writes a Commodore PRG header preceding the output file, which consists of two bytes in little-endian order, defining the load address of the program.

`-coco-ml`

Writes a Tandy Color Computer machine language file, which has a header with load address and length for each section and is terminated by a trailer with the execution address.

`-dragon-bin`

Writes a Dragon DOS header preceding the output file, where the file type is set to \$02 for binary. The load address is taken from the first section's start address. This will also be the execute-address, when not specified otherwise. Refer to option `-exec`.

`-exec=<symbol>`

Use the given symbol `<symbol>` as entry point of the program, for those output format headers which support it. Otherwise this option will be silently ignored. Omitting this option will usually define the execution address to be the same as the load address.

`-foenix-pgx`

Writes a simple, single-segment format for the 65816-based Foenix computers. The header defines the program's load address, which is also the start address.

`-foenix-pgz`

Write a multi-segment format for the 65816-based Foenix computers. The format is derived from binary format used by Western Design Center's C compiler. Every segment is stored with load address and size, and there is also a start address defined.

- oric-mc** Writes a machine code file header for Oric-1, Oric-Atmos and compatible systems. It includes the file type and name, as well as the first and last address of the program to load. Note, that the name defaults to the output file name, limited to 15 characters. A ".tap" extension will be removed automatically.
- oric-mcx** Same as **-oric-mc**, but sets the auto-execute flag in the header.
- start=<address>** Set the start address for the default section, when no **section** or **org** directive was given.

16.3 General

This output module outputs the contents of all sections as simple binary data, by default without any header or additional information. When there are multiple sections, they must not overlap. Gaps between sections are filled with zero bytes, when not using a special header format, like Atari COM. Undefined symbols are not allowed.

16.4 Known Problems

Some known problems of this module at the moment:

- None.

16.5 Error Messages

This module has the following error messages:

- 3001: sections <%s>:%llx-%llx and <%s>:%llx-%llx must not overlap
- 3007: undefined symbol <%s>
- 3009: undefined symbol <%s> at %s+0x%lx, reloc type %d
- 3010: section <%s>: alignment padding (%lu) not a multiple of %lu at 0x%llx
- 3013: reloc type %d, mask 0x%lx to symbol %s + 0x%lx does not fit into %u bits
- 3021: all sections are absolute, nothing to relocate

17 Motorola srecord output module

This chapter describes the Motorola srecord output module which can be selected with the `-Fsrec` option.

17.1 Legal

This module is written in 2015 by Joseph Zatarski and is covered by the vasm copyright without modifications.

17.2 Additional options for this module

- `-crlf` Enforce Carriage-Return and Line-Feed ("`\r\n`") line endings. Default is to use the host's line endings.
- `-exec[=<symbol>]`
 Use the given symbol `<symbol>` as entry point of the program. This start address will be written into the trailer record, which is otherwise zero. When the symbol assignment is omitted, then the default symbol `start` will be used.
- `-s19` Writes S1 data records and S9 trailers with 16-bit addresses.
- `-s28` Writes S2 data records and S8 trailers with 24-bit addresses.
- `-s37` Writes S3 data records and S7 trailers with 32-bit addresses. This is the default setting.

17.3 General

This output module outputs the contents of all sections in Motorola srecord format, which is a simple ASCII output of hexadecimal digits. Each record starts with 'S' and a one-digit ID. It is followed by the data and terminated by a checksum and a newline character. Every section starts with a new header record.

17.4 Known Problems

Some known problems of this module at the moment:

- A new header is written for every new section. This may cause compatibility issues.

17.5 Error Messages

This module has the following error messages:

- 3007: undefined symbol `<%s>`
- 3010: section `<%s>`: alignment padding (`%lu`) not a multiple of `%lu` at `0x%llx`
- 3012: address `0x%llx` out of range for selected format

18 Intel hex output module

This chapter describes the Intel Hex output module which can be selected with the `-Fihex` option.

18.1 Legal

This module is written in 2020 by Rida Dzhaafar and is covered by the vasm copyright without modifications.

18.2 Additional options for this module

- `-crlf` Enforce Carriage-Return and Line-Feed ("`\r\n`") line endings. Default is to use the host's line endings.
- `-i8hex` Selects a format supporting 16-bit address space (default).
- `-i16hex` Selects a format supporting 20-bit address space.
- `-i32hex` Selects a format supporting 32-bit address space.
- `-record-size=<n>`
 Sets the number of bytes per record to `n`. Defaults to 32 bytes.

18.3 General

This output module outputs the contents of all sections in Intel hex format, which is a simple ASCII output of hexadecimal digits.

18.4 Known Problems

Some known problems of this module at the moment:

- None?

18.5 Error Messages

This module has the following error messages:

- 3001: sections `<%s>:%llx-%llx` and `<%s>:%llx-%llx` must not overlap
- 3002: output module doesn't support cpu `%s`
- 3007: undefined symbol `<%s>`
- 3012: address `0x%llx` out of range for selected format

19 C #define output module

This chapter describes the C #define output module which can be selected with the `-Fcdef` option.

19.1 Legal

This module is written in 2020 by Volker Barthelmann and is covered by the vasm copyright without modifications.

19.2 Additional options for this module

There are currently no additional options for this output module.

19.3 General

This output module outputs the values of absolute symbols as a series of `#define` directives that can be included in a C compiler. No code is generated.

19.4 Known Problems

Some known problems of this module at the moment:

- None.

19.5 Error Messages

This module has no error messages:

20 Wozmon output module

This chapter describes the wozmon output module which can be selected with the `-Fwoz` option.

20.1 Legal

This module is written in 2023 by anomie-p and is covered by the vasm copyright without modifications.

20.2 Contact

The author of this module may be contacted for bug reports:

- anomie-p (anomie-p@protonmail.com)

20.3 Additional options for this module

There are no additional options for this module.

20.4 General

This output module outputs the contents of all sections as wozmon monitor commands, which is a simple ASCII output of hexadecimal digits.

The output is suitable for an ASCII transfer via serial connection to a system running wozmon. Character and/or line delays are likely to be necessary for a successful transfer.

The wozmon command parser converts up to sixteen bit hexadecimal values. An error containing the maximum out of range address is reported if a sixteen bit address space is exceeded.

20.5 Known Problems

Some known problems of this module at the moment:

- None.

20.6 Error Messages

This module has the following error messages:

- 3001: sections `<%s>:%llx-%llx` and `<%s>:%llx-%llx` must not overlap
- 3002: output module doesn't support cpu `%s`
- 3007: undefined symbol `<%s>`
- 3012: address `0x%llx` out of range for selected format

21 m68k cpu module

This chapter documents the backend for the Motorola M68k/CPU32/ColdFire microprocessor family.

21.1 Legal

This module is written in 2002-2023 by Frank Wille and is covered by the vasm copyright without modifications.

21.2 Additional options for this module

Note, that the order on the command line may be important when specifying options. For example, if you specify `-devpac` compatibility mode behind enabling some optimization options, the Devpac-mode might disable these optimizations again.

This module provides the following additional options:

21.2.1 CPU selections

- `-m68000` Generate code for the MC68000 CPU.
- `-m68008` Generate code for the MC68008 CPU.
- `-m68010` Generate code for the MC68010 CPU.
- `-m68020` Generate code for the MC68020 CPU.
- `-m68030` Generate code for the MC68030 CPU.
- `-m68040` Generate code for the MC68040 CPU.
- `-m68060` Generate code for the MC68060 CPU.
- `-m68020up` Generate code for the MC68020-68060 CPU. Be careful with instructions like PFLUSHA, which exist on 68030 and 68040/060 with a different opcode (vasm will use the 040/060 version).
- `-m68080` Generate code for the Apollo Core AC68080 CPU.
- `-mcpu32` Generate code for the CPU32 family (MC6833x, MC6834x, etc.).
- `-mcf5...`
- `-m5...` Generate code for a ColdFire family CPU. The following types are recognized: 5202, 5204, 5206, 520x, 5206e, 5207, 5208, 5210a, 5211a, 5212, 5213, 5214, 5216, 5224, 5225, 5232, 5233, 5234, 5235, 523x, 5249, 5250, 5253, 5270, 5271, 5272, 5274, 5275, 5280, 5281, 528x, 52221, 52553, 52230, 52231, 52232, 52233, 52234, 52235, 52252, 52254, 52255, 52256, 52258, 52259, 52274, 52277, 5307, 5327, 5328, 5329, 532x, 5372, 5373, 537x, 53011, 53012, 53013, 53014, 53015, 53016, 53017, 5301x, 5407, 5470, 5471, 5472, 5473, 5474, 5475, 547x, 5480, 5481, 5482, 5483, 5484, 5485, 548x, 54450, 54451, 54452, 54453, 5445x.
- `-mcfv2` Generate code for the V2 ColdFire core. This option selects ISA_A (no hardware division or MAC), which is the most limited ISA supported by 5202, 5204 and 5206. All other ColdFire chips are backwards compatible to V2.

- mcfv3** Generate code for the V3 ColdFire core. This option selects ISA_A+, hardware division MAC and EMAC instructions, which are supported by nearly all V3 CPUs, except the 5307.
- mcfv4** Generate code for the V4 ColdFire core. This option selects ISA_B and MAC as supported by the 5407.
- mcfv4e** Generate code for the V4e ColdFire core. This option selects ISA_B, USP-, FPU-, MAC- and EMAC-instructions (no hardware division) as supported by all 547x and 548x CPUs.
- m68851** Generate code for the MC68851 MMU. May be used in combination with another **-m** option.
- m68881** Generate code for the MC68881 FPU. May be used in combination with another **-m** option.
- m68882** Generate code for the MC68882 FPU. May be used in combination with another **-m** option.
- no-fpu** Ignore any FPU options or directives, which has the effect that no 68881/2 FPU instructions will be accepted. This option can override the default of **-gas** to enable the FPU.

21.2.2 Optimization options

- no-opt** Disable all optimizations. Can be seen as a main switch to ignore all other optimization options on the command line and in the source.
- opt-allbra**
When specified the assembler will also try to optimize branch instructions which already have a valid size extension. This option is automatically enabled in **-phxass** mode.
- opt-brajump**
Translate relative branch instructions, whose destination is in a different section, into absolute jump instructions.
- opt-clr** Enables optimization from **MOVE #0,<ea>** into **CLR <ea>** for the MC68000. Note that **CLR** will execute a read-modify-write cycle on the 68000, so it is disabled by default. With 68010 and higher this is a generic standard optimization.
- opt-div** Unsigned immediate divisors, which are a power of two (from 2 to 256), are optimized to shifts. Divisions by 1 are replaced by **TST.L Dn** (32-bit) or **MVZ.W Dn,Dn** (16-bit, ColdFire only). Divisions by -1 are replaced by **NEG.L Dn** (32-bit) or by a combination of **NEG.W Dn** and **MVZ.W Dn,Dn** (16-bit, ColdFire only). This optimization will leave the flags in a different state as can normally be expected after a division instruction.
- opt-fconst**
Floating point constants are loaded with the lowest precision possible. This means that **FMOVE.D #1.0,FP0** would be optimized to **FMOVE.S #1.0,FP0**, because it is faster and shorter at the same precision. The optimization will be performed on all FPU instructions with immediate addressing mode. When an

FDIV-family instruction (FSDIV, FDDIV, FSGLDIV) is detected it will additionally be checked if the immediate constant is a power of 2 and then converted into FMUL #1/c,FPn.

-opt-jbra

JMP and JSR instructions to external labels will be converted into BRA.L and BSR.L, when the selected CPU is 68020 or higher (or CPU32).

-opt-lsl Allows optimization of LSL #1 into ADD. It is also needed to optimize ASL #2 and LSL #2 into two ADD instructions (together with **-opt-speed**). These optimizations may modify the V-flag, which might not be intended.

-opt-movem

Enables optimization from MOVEM <ea>,Rn into MOVE <ea>,Rn (or the other way around). May also optimize MOVEM with two registers into two separate MOVE instructions, when advantageous for the currently selected CPU. This optimization will modify the flags when the destination is no address register.

-opt-mul Immediate multiplication factors, which are a power of two (from 2 to 256), are optimized to shifts. Multiplications with zero are replaced by a MOVEQ #0,Dn, with -1 are replaced by a NEG.L Dn and with 1 by EXT.L Dn or TST.L Dn (long-form). Not all optimizations are available for all cpu types (e.g. MULU.W can only be optimized on ColdFire by using the MVZ.W instruction). This optimization will leave the flags in a different state as can normally be expected after a multiplication instruction, and the size of the optimized code may be bigger than before in some situations (e.g. MULS.W #4,Dn). The latter will additionally require the **-opt-speed** flag.

-opt-nmoveq

Optimizes MOVE.L #x,Dn into a combination of MOVEQ and NEG.W, which works for ranges from \$ff81<=x<=\$ffff and \$ffff0001<=x<=\$ffff0080. Note that this optimization flips the N-flag!

-opt-pea Enables optimization from MOVE #x,-(SP) into PEA x. This optimization will leave the flags unmodified, which might not be intended.

-opt-speed

Optimize for speed, even if this would increase code size. For example it enables optimization of ASL.W #2,Dn into two ADD.W Dn,Dn instructions. Or MULS.W #-4,Dn into EXT.L Dn + ASL.L #2,Dn + NEG.L Dn.

-opt-size

Optimize for size, even if this would make the code slower. This enables for example optimization of MOVE.L #x,Dn into MOVEQ #x>>n,Dn + LSL.W #n,Dn. It is mostly used together with other optimization flags.

-opt-st Enables optimization from MOVE.B #-1,<ea> into ST <ea>. This optimization will leave the flags unmodified, which might not be intended.

-sc Small code model. All JMP and JSR instructions to external labels will be converted into 16-bit PC-relative jumps.

- sd** References to absolute symbols in a small data section (named "__MERGED") are optimized into a base-relative addressing mode using the current base register set by an active **NEAR** directive. This option is automatically enabled in **-phxass** mode.
- showcrit** Print all critical optimizations which have side effects. Among those are **-opt-lsl**, **-opt-mul**, **-opt-st**, **-opt-pea**, **-opt-movem** and **-opt-clr**.
- showopt** Print all optimizations and translations vasm is doing (same as **opt ow+**).

In its default setting (no **-devpac** or **-phxass** option) vasm performs the following optimizations:

- Absolute to PC-relative.
- Branches without explicit size.
- Displacements (32 to 16 bit, (0,An) to (An), etc).
- Optimize floating point constants to the lowest possible precision.
- Many instruction optimizations which are safe.

21.2.3 Other options

- conv-brackets** Brackets ('[' and ']') in an operand are automatically converted into parentheses ('(' and ')') as long as the CPU is 68000 or 68010. This is a compatibility option for some old assemblers.
- devpac** All options are initially set to be Devpac compatible. Which means that all optimizations are disabled, no debugging symbols will be written and vasm will warn about any optimization being done. When symbol output is enabled by **opt d+**, then the TOS symbol table defaults to standard DRI format (limited to 8 characters). Shift-right operations are performed using an unsigned 32-bit value. Other options are the same as vasm's defaults. The symbol **__G2** is defined, which contains information about the selected cpu type. The symbol **__LK** reflects the type of output file generated. Which is 0 for TOS executables, 1 for DRI objects, 2 for GST objects, 3 for AmigaDOS objects and 4 for AmigaDOS executables. All other formats are represented by 99, as they are unknown to Devpac. It will also automatically enable **-guess-ext** and **-nodpc**.
- elfregs** Register names are preceded by a '%' to prevent confusion with symbol names.
- extsd** Recognize small data references in all 020+ extended addressing modes using 16-bit displacements on the base register. By default only the 16-bit address register displacement addressing mode can be used with small data (for compatibility reasons).
- gas** Enable additional GNU-as compatibility mnemonics, like **mov**, **movm** and **jra**. Also accepts **|** instead of **;** for comments. GNU-as compatibility mode selects the 68020 CPU and 68881/2 FPU by default and enables **-opt-jbra**.

- guess-ext**
Accept illegal size extensions for an instruction, as long as the instruction is unsized or there is just a single size possible. This is the default setting in PhxAss and Devpac compatibility mode.
- kick1hunks**
Prevents optimization of JMP/JSR to 32-bit PC-relative (BRA/BSR).
- nodpc**
Do not attempt to encode absolute PC-displacements directly. Example: 10(PC)
- no-typechk**
Do not check the size and type of expressions (OPT t-). Example: dc.b 300
- phxass**
PhxAss-compatibilty mode. The "current PC symbol" (e.g. * in mot-syntax module) is set to the instruction's address + 2 whenever an instruction is parsed. According to the current cpu setting the symbols __CPU, __FPU and __MMU are defined. JMP/JSR (label,PC) will never be optimized (into a branch, for example). It will also automatically enable -opt-allbra, -sd and -guess-ext.
- rangewarnings**
Values which are out of range usually produce an error. With this option the errors 2026, 2030, 2033 and 2037 will be displayed as a warning, allowing the user to create an object file.
- regsymredef**
Allow redefining register symbols with EQUR. This should only be used for compatibility with old sources. Not many assemblers support that.
- sdreg=<n>**
Set the small data base register to An. <n> is valid between 0 and 6.
- sgs**
Additionally allow immediate operands to be prefixed by & instead of just by #. This syntax was used by the SGS assembler.

21.3 General

This backend accepts M68k and CPU32 instructions as described in Mototola's M68000 family Programmer's Reference Manual. Additionally it supports ColdFire instructions as described in Motorola's ColdFire Microprocessor Family Programmer's Reference Manual.

The syntax for the scale factor in ColdFire MAC instructions is << for left- and >> for right-shift. The scale factor may be appended as an optional operand, when needed. Example: mac d0.l,d1.u,<<.

The mask flag in MAC instructions is written as & and is appended directly to the effective address operand. Example: mac d0,d1,(a0)&,d2.

The target address type is 32bit. Floating point constants in instructions and data are supported and encoded in IEEE format.

Default alignment for instructions is 2 bytes. The default alignment for data is 2 bytes, when the data size is larger than 8 bits.

21.4 Internal symbols

Depending on the selected cpu type the `__VASM` symbol will have a value defined by the following bits:

bit 0	MC68000 instruction set. Also used by MC6830x, MC68322, MC68356.
bit 1	MC68010 instruction set.
bit 2	MC68020 instruction set.
bit 3	MC68030 instruction set.
bit 4	MC68040 instruction set.
bit 5	MC68060 instruction set.
bit 6	MC68881 or MC68882 FPU.
bit 7	MC68851 PMMU.
bit 8	CPU32. Any MC6833x or MC6834x CPU.
bit 9	ColdFire ISA_A.
bit 10	ColdFire ISA_A+.
bit 11	ColdFire ISA_B.
bit 12	ColdFire ISA_C.
bit 13	ColdFire hardware division support.
bit 14	ColdFire MAC instructions.
bit 15	ColdFire enhanced MAC instructions.
bit 16	ColdFire USP register.
bit 17	ColdFire FPU instructions.
bit 18	ColdFire MMU instructions.
bit 20	Apollo Core AC68080 instruction set.

The following symbols are defined for compatibility with other assemblers, so their function is not described here.

Devpac	<code>__G2</code> , <code>__LK</code>
PhxAss	<code>__CPU</code> , <code>__FPU</code> , <code>__MMU</code> , <code>__OPTC</code>
BAsm	<code>_MOVEMBYTES</code> , <code>__MOVEMREGS</code>

21.5 Extensions

This backend extends the selected syntax module by the following directives:

- .sdreg <An>**
Equivalent to **near <An>**.
- basereg <expression>,<An>**
Starts a block of base-relative addressing through register **An** (remember that A7 is not allowed as a base register). The developer has to make sure that **<expression>** is placed into **An** first, while the assembler automatically subtracts **<expression>**, which is usually a program label with an optional offset, from each displacement in a **(d,An)** addressing mode. **basereg** has priority over the **near** directive. Its effect can be suspended with the **endb** directive. It is allowed to use several base registers in parallel.
- cpu32** Generate code for the CPU32 family.
- endb <An>** Ends a **basereg** block and suspends its effect onto the specified base register **An**. It may be reused with a different base expression thereafter (refer to **basereg**).
- far** Disables small data (base-relative) mode. All data references will be absolute.
- fpu <cpID>**
Enables 68881/68882 FPU code generation. The **<cpID>** is inserted into the FPU instructions to select the correct coprocessor. Note that **<cpID>** is always 1 for the on-chip FPUs in the 68040 and 68060. A **<cpID>** of zero will disable FPU code generation.
- initnear** Initializes the selected small data base register. In contrast to PhxAss, where this directive comes from, just a reference to **_LinkerDB** is generated, which has to be resolved by a linker.
- machine <cpu_type>**
Makes the assembler generate code for **<cpu_type>**, which can be the following: 68000, 68010, 68020, 68030, 68040, 68060, 68080, 68851, 68881, 68882, **cpu32**. And various ColdFire CPUs, starting with 5....
- mc68000** Generate code for the MC68000 CPU.
- mc68010** Generate code for the MC68010 CPU.
- mc68020** Generate code for the MC68020 CPU.
- mc68030** Generate code for the MC68030 CPU.
- mc68040** Generate code for the MC68040 CPU.
- mc68060** Generate code for the MC68060 CPU.
- ac68080** Generate code for the Apollo Core AC68080 FPGA CPU.
- mcf5...** Generate code for a ColdFire CPU. The recognized models are listed in the assembler-options section.
- near [<An>]**
Enables small data (base-relative) mode and sets the base register to **An**. **near** without an argument will reactivate a previously defined small data mode, which might have been switched off by a **far** directive.

near code All JMP and JSR instructions to external labels will be converted into 16-bit PC-relative jumps. The small code mode can be switched off by a **far** directive.

opt <option>[,<option>...]

Sets Devpac-compatible options. When option **-phxass** is given, then it will parse PhxAss options instead (which is discouraged for new code, so there is no detailed description here). Most supported Devpac2-style options are always suffixed by a **+** or **-** to enable or disable the option:

- a** Automatically optimize absolute to PC-relative references. Default is off in Devpac-comptability mode, otherwise on.
- c** Case-sensitivity for all symbols, instructions and macros. Default is on.
- d** Include all symbols for debugging in the output file. May also generate line debugging information in some output formats. Default is off in Devpac-comptability mode, otherwise on.
- l** Generate a linkable object file. The default is defined by the selected output format via the assembler's **-F** option. This option was supported by Devpac-Amiga only.
- o** Enable all optimizations (o1 to o12), or disable all optimizations. The default is that all are disabled in Devpac-compatibility mode and enabled otherwise. When running in native vasm mode this option will also enable PC-relative (**opt a**) and the following safe vasm-specific optimizations (see below): **og**, **of**.
- o1** Optimize branches without an explicit size extension.
- o2** Standard displacement optimizations (e.g. **(0,An) -> (An)**).
- o3** Optimize absolute addresses to short words.
- o4** Optimize **move.l** to **moveq**.
- o5** Optimize **add #x** and **sub #x** into their quick forms.
- o6** No effect in vasm.
- o7** Convert **bra.b** to **nop**, when branching to the next instruction.
- o8** Optimize 68020+ base displacements to 16 bit.
- o9** Optimize 68020+ outer displacements to 16 bit.
- o10** Optimize **add/sub #x,An** to **leaq**.
- o11** Optimize **leaq (d,An),An** to **addq/subq**.
- o12** Optimize **<op>.l #x,An** to **<op>.w #x,An**.
- ow** Show all optimizations being performed. Default is on in Devpac-compatibility mode, otherwise off.
- p** Check if code is position independent. This will cause an error on each relocation being required. Default is off.

s	Include symbols in listing file. Default is on.
t	Check size and type of all expressions. Default is on.
w	Show assembler warnings. Default is on.
x	For Amiga hunk format objects x+ strips local symbols from the symbol table (symbols without xdef). For Atari TOS executables this will enable the extended (HiSoft) DRI symbol table format, which allows symbols with up to 22 characters. DRI standard only supports 8 characters.

Devpac options without +/- suffix:

l<n> Sets the output format (Devpac Atari only). Currently without effect.

p=<type>[/<type>]
Sets the CPU type to any model vasm supports (original Devpac only allowed 68000-68040, 68332, 68881, 68882 and 68851).

Also the following Devpac3-style options are supported:

autopc	Corresponds to a+ .
case	Corresponds to c+ .
chkpc	Corresponds to p+ .
debug	Corresponds to d+ .
symtab	Corresponds to s+ .
type	Corresponds to t+ .
warn	Corresponds to w+ .
xdebug	Corresponds to x+ .
noautopc	Corresponds to a- .
nocase	Corresponds to c- .
nochkpc	Corresponds to p- .
nodebug	Corresponds to d- .
nosymtab	Corresponds to s- .
notype	Corresponds to t- .
nowarn	Corresponds to w- .
noxdebug	Corresponds to x- .

The following options are vasm specific and should not be used when writing portable source. Using **opt o+** or **opt o-** in Devpac mode only toggles **og** and **of**.

ob Convert absolute jumps to external labels into long-branches (refer to **-opt-jbra**).

<code>oc</code>	Enable optimizations to CLR (refer to <code>-opt-clr</code>).
<code>od</code>	Enable optimization of divisions into shifts (refer to <code>-opt-div</code>).
<code>of</code>	Enable immediate float constant optimizations (refer to <code>-opt-fconst</code>).
<code>og</code>	Enable generic vasm optimizations. This includes all safe optimizations which cannot be controlled by another option.
<code>oj</code>	Enable branch to jump translations (refer to <code>-opt-brajmp</code>).
<code>ol</code>	Enable shift optimizations to ADD (refer to <code>-opt-lsl</code>).
<code>om</code>	Enable MOVEM optimizations (refer to <code>-opt-movem</code>).
<code>on</code>	Enable small data optimizations. References to absolute symbols in a small data section (named " <code>__MERGED</code> ") are optimized into a base-relative addressing mode (refer to <code>-sd</code>).
<code>op</code>	Enable optimizations to PEA (refer to <code>-opt-pea</code>).
<code>oq</code>	Optimizes <code>MOVE.L</code> into a combination of <code>MOVEQ</code> and <code>NEG.W</code> (refer to <code>-opt-nmoveq</code>).
<code>os</code>	Optimize for speed before optimizing for size (refer to <code>-opt-speed</code>).
<code>ot</code>	Enable optimizations to ST (refer to <code>-opt-st</code>).
<code>ox</code>	Enable optimization of multiplications into shifts (refer to <code>-opt-mul</code>).
<code>oz</code>	Enable optimization for size, even if the code becomes slower (refer to <code>-opt-size</code>).

The default state is 'off' for all these vasm specific options, except for `of` and `og`, which are 'on'.

The following directives are only available for the Motorola syntax module:

`<symbol> equ <Rn>`

Define a new symbol named `<symbol>` and assign the data or address register `Rn`, which can be used from now on in operands. When 68080 code generation is enabled, also `Bn` base address registers and `En` vector registers are allowed to be assigned. Note that a register symbol must be defined before it can be used!

`<symbol> eql <reglist>`

Equivalent to `<symbol> reg <reglist>`.

`<symbol> feqr <FPn>`

Define a new symbol named `<symbol>` and assign the FPU register `FPn`, which can be used from now on in operands. Note that a register symbol must be defined before it can be used!

`<symbol> feql <reglist>`

Equivalent to `<symbol> freg <reglist>`.

<symbol> freg <reglist>

Defines a new symbol named <symbol> and assign the FPU register list <reglist> to it. Registers in a list must be separated by a slash (/) and ranges or registers can be defined by using a hyphen (-). Examples for valid FPU register lists are: fp0-fp7, fp1-3/fp5/fp7, fpiar/fpcr.

<symbol> reg <reglist>

Defines a new symbol named <symbol> and assign the register list <reglist> to it. Registers in a list must be separated by a slash (/) and ranges or registers can be defined by using a hyphen (-). Examples for valid register lists are: d0-d7/a0-a6, d3-6/a0/a1/a4-5.

21.6 Optimizations

21.6.1 Operand optimizations

This backend performs the following operand optimizations:

- (0,An) optimized to (An).
- (d16,An) translated to (bd32,An,ZDn.w), when d16 is not between -32768 and 32767 and the selected CPU allows it (68020 up or CPU32).
- (d16,PC) translated to (bd32,PC,ZDn.w), when d16 is not between -32768 and 32767 and the selected CPU allows it (68020 up or CPU32).
- (d8,An,Rn) translated to (bd,An,Rn), when d8 is not between -128 and 127 and the selected CPU allows it (68020 up or CPU32).
- (d8,PC,Rn) translated to (bd,PC,Rn), when d8 is not between -128 and 127 and the selected CPU allows it (68020 up or CPU32).
- <exp>.l optimized to <exp>.w, when <exp> is absolute and between -32768 and 32767.
- <exp>.w translated to <exp>.l, when <exp> is a program label or absolute and not between -32768 and 32767.
- (0,An,...) optimized to (An,...) (which means the base displacement will be suppressed). This allows further optimization to (An), when the index is suppressed.
- (bd16,An,...) translated to (bd32,An,...), when bd16 is not between -32768 and 32767.
- (bd32,An,...) optimized to (bd16,An,...), when bd16 is between -32768 and 32767.
- (bd32,An,ZRn) optimized to (d16,An), when bd32 is between -32768 and 32767, and the index is suppressed (zero-Rn).
- (An,ZRn) optimized to (An), when the index is suppressed.
- (0,PC,...) optimized to (PC,...) (which means the base displacement will be suppressed).
- (bd16,PC,...) translated to (bd32,PC,...), when bd16 is not between -32768 and 32767.
- (bd32,PC,...) optimized to (bd16,PC,...), when bd16 is between -32768 and 32767.
- (bd32,PC,ZRn) optimized to (d16,PC), when bd32 is between -32768 and 32767, and the index is suppressed (zero-Rn).

- ([0,Rn,...],...) optimized to ([An,...],...) (which means the base displacement will be suppressed).
- ([bd16,Rn,...],...) translated to ([bd32,An,...],...), when bd16 is not between -32768 and 32768.
- ([bd32,Rn,...],...) optimized to ([bd16,An,...],...), when bd32 is between -32768 and 32768.
- ([...],0) optimized to ([...]) (which means the outer displacement will be suppressed).
- ([...],od16) translated to ([...],od32), when od16 is not between -32768 and 32767.
- ([...],od32) translated to ([...],od16), when od32 is between -32768 and 32767.

Note that an operand optimization will only take place when a displacement's size was not enforced by the developer through an explicit size extension (e.g. (4.1,a0))!

21.6.2 Instruction optimizations

This backend performs the following instruction optimizations and translations:

- <op>.L #x,An optimized to <op>.W #x,An, when x is between -32768 and 32767.
- ADD.? #x,<ea> optimized to ADDQ.? #x,<ea>, when x is between 1 and 8.
- ADD.? #x,<ea> optimized to SUBQ.? #x,<ea>, when x is between -1 and -8.
- ADDA.? #0,An and SUBA.? #0,An will be deleted.
- ADDA.? #x,An translated to LEA (x,An),An, when x is between -32768 and 32767.
- ANDI.L #\$ff,Dn optimized to MVZ.B Dn,Dn, for ColdFire ISA_B/C.
- ANDI.L \$ffff,Dn optimized to MVZ.W Dn,Dn, for ColdFire ISA_B/C.
- ANDI.? #0,<ea> optimized to CLR.? <ea>, when allowed by the option -opt-clr or a different CPU than the MC68000 was selected.
- ANDI.? #-1,<ea> optimized to TST.? <ea>.
- ASL.? #1,Dn optimized to ADD.? Dn,Dn for 68000 and 68010.
- ASL.? #2,Dn optimized into a sequence of two ADD.? Dn,Dn for 68000 and 68010, when the operation size is either byte or word and the options -opt-speed and -opt-lsl are given.
- B<cc> <label> translated into a combination of B!<cc> *+8 and JMP <label>, when <label> is not defined in the same section (and option -opt-brajmp is given), or outside the range of -32768 to 32767 bytes from the current address when the selected CPU is not 68020 up, CPU32 or ColdFire ISA_B/C.
- B<cc> <label> is automatically optimized to 8-bit, 16-bit or 32-bit (68020 up, CPU32, MCF5407 only), whatever fits best. When the selected CPU doesn't support 32-bit branches it will try to change the conditional branch into a B!<cc> *+8 and JMP <label> sequence.
- BRA <label> translated to JMP <label>, when <label> is not defined in the same section (and option -opt-brajmp is given), or outside the range of -32768 to 32767 bytes from the current address when the selected CPU is not 68020 up, CPU32 or ColdFire ISA_B/C.

- BSR <label> translated to JSR <label>, when <label> is not defined in the same section (and option `-opt-brajmp` is given), or outside the range of -32768 to 32767 bytes from the current address when the selected CPU is not 68020 up, CPU32 or ColdFire ISA_B/C.
- <cp>B<cc> <label> is automatically optimized to 16-bit or 32-bit, whatever fits best. <cp> means coprocessor and is P for the PMMU and F for the FPU.
- CLR.L Dn optimized to MOVEQ #0,Dn.
- CMP.? #0,<ea> optimized to TST.? <ea>. The selected CPU type must be MC68020 up, ColdFire or CPU32 to support address register direct as effective address (<ea>).
- DIVS.W/DIVU.W #1,Dn optimized to MVZ.W Dn,Dn, for ColdFire ISA_B/C (`-opt-div`).
- DIVS.W #-1,Dn optimized to the sequence of NEG.W Dn and MVZ.W Dn,Dn (`-opt-div` and `-opt-speed`).
- DIVS.L/DIVU.L #1,Dn optimized to TST.L Dn (`-opt-div`).
- DIVS.L #-1,Dn optimized to NEG.L Dn (`-opt-div`).
- DIVU.L #2..256,Dn optimized to LSR.L #x,Dn (`-opt-div`).
- EORI.? #-1,<ea> optimized to NOT.? <ea>.
- EORI.? #0,<ea> optimized to TST.? <ea>.
- FMOVEM.? <reglist> is deleted when the register list was empty.
- FxDIV.? #m,FPn optimized to FxMUL.? #1/m,FPn when m is a power of 2 and option `-opt-fconst` is given.
- JMP <label> optimized to BRA.? <label>, when <label> is defined in the same section and in the range of -32768 to 32767 bytes from the current address. Note that JMP (<lab>,PC) is never optimized, with the intention to preserve jump-tables.
- JSR <label> optimized to BSR.? <label>, when <label> is defined in the same section and in the range of -32768 to 32767 bytes from the current address. Note that JSR (<lab>,PC) is never optimized, with the intention to preserve jump-tables.
- LEA 0,An optimized to SUBA.L An,An.
- LEA (0,An),An and LEA (An),An will be deleted.
- LEA (d,An),An is optimized to ADDQ.L #d,An when d is between 1 and 8 and to SUBQ.L #-d,An when d is between -1 and -8.
- LEA (d,Am),An will be translated into a combination of MOVEA and ADDA.L for 68000 and 68010, when d is lower than -32768 or higher than 32767. The MOVEA will be omitted when Am and An are identical. Otherwise `-opt-speed` is required.
- LINK.L An,#x optimized to LINK.W An,#x, when x is between -32768 and 32767.
- LINK.W An,#x translated to LINK.L An,#x, when x is not between -32768 and 32767 and selected CPU supports this instruction.
- LSL.? #1,Dn optimized to ADD.? Dn,Dn for 68000 and 68010, when option `-opt-lsl` is given.
- LSL.? #2,Dn optimized into a sequence of two ADD.? Dn,Dn for 68000 and 68010, when the operation size is either byte or word and the options `-opt-speed` and `-opt-lsl` are given.

- `MOVE.? #0,<ea>` optimized to `CLR.? <ea>`, when allowed by the option `-opt-clr` or a different CPU than the MC68000 was selected.
- `MOVE.? #x,-(SP)` optimized to `PEA x`, when allowed by the option `-opt-pea`. The move-size must not be byte (`.b`).
- `MOVE.B #-1,<ea>` optimized to `ST <ea>`, when allowed by the option `-opt-st`.
- `MOVE.L #x,Dn` optimized to `MOVEQ #x,Dn`, when `x` is between -128 and 127.
- `MOVE.L #x,Dn` optimized to the sequence of `MOVEQ #x>>1,Dn` and `ADD.W Dn,Dn`, when `128<=x<=254` and `x` is even.
- `MOVE.L #x,Dn` optimized to the sequence of `MOVEQ #x^$ff,Dn` and `NOT.B Dn`, when `128<=x<=255` and the option `-opt-nmoveq` was set.
- `MOVE.L #x,Dn` optimized to the sequence of `MOVEQ #x>>16,Dn` and `SWAP Dn`, when `$10000<=x<=$7f0000` or `$ff80ffff<=x<=$fffeffff`.
- `MOVE.L #x,Dn` optimized to the sequence of `MOVEQ #y,Dn` and `NEG.W Dn`, when `$ff81<=x<=$ffff` or `$ffff0001<=x<=$ffff0080` and the option `-opt-nmoveq` was set.
- `MOVE.L #x,Dn` optimized to the sequence of `MOVEQ #x>>n,Dn` and `LSL.W #n,Dn`, when `$0100<=x<=$7f00` and the LSB is zero and `-opt-size` was set together with standard optimizations.
- `MOVE.L #x,<ea>` optimized to `MOV3Q #x,<ea>`, for ColdFire `ISA_B` and `ISA_C`, when `x` is -1 or between 1 and 7.
- `MOVEA.? #0,An` optimized to `SUBA.L An,An`.
- `MOVEA.L #x,An` optimized to `MOVEA.W #x,An`, when `x` is between -32768 and 32767.
- `MOVEA.L #label,An` optimized to `LEA label,An`, which could allow further optimization to `LEA label(PC),An`.
- `MOVEM.? <reglist>` is deleted, when the register list was empty.
- `MOVEM.? <ea>,An` optimized to `MOVE.? <ea>,An`, when the register list only contains a single address register.
- `MOVEM.? <ea>,Rn` optimized to `MOVE.? <ea>,Rn` and `MOVEM.? Rn,<ea>` optimized to `MOVE.? Rn,<ea>`, when allowed by the option `-opt-movem` or when just loading an address register.
- `MOVEM.? <ea>,Rm/Rn` and `MOVEM.? Rm/Rn,<ea>` are optimized into a sequence of two `MOVE` instructions when advantageous for the currently selected CPU. For example, for 68000 and 68010 it is no advantage to optimize `MOVEM Rm/Rn,-(An)`, and addressing modes with displacements or absolute addresses are optimized for 68040 only (may additionally require `opt-speed`).
- `MULS.?/MULU.? #0,Dn` optimized to `MOVEQ #0,Dn` (`-opt-mul`).
- `MULS.?/MULU.? #1,Dn` is deleted (`-opt-mul`).
- `MULS.W #-1,Dn` optimized to the sequence `EXT.L Dn` and `NEG.L Dn` (`-opt-mul` and `-opt-speed`).
- `MULS.L #-1,Dn` optimized to `NEG.L Dn` (`-opt-mul`).
- `MULS.W #2..256,Dn` optimized to the sequence `EXT.L Dn` and `ASL.L #x,Dn` (`-opt-mul` and `-opt-speed`).

- `MULS.W #2..256,Dn` optimized to the sequence `EXT.L Dn, ASL.L #x,Dn` and `NEG.L Dn` (`-opt-mul` and `-opt-speed`).
- `MULS.L #2..256,Dn` optimized to `ASL.L #x,Dn` (`-opt-mul`).
- `MULS.L #2..256,Dn` optimized to the sequence `ASL.L #x,Dn` and `NEG.L Dn` (`-opt-mul` and `-opt-speed`).
- `MULU.W #2..256,Dn` optimized to the sequence `MVZ.W Dn,Dn` and `ASL.L #x,Dn` for Cold-Fire ISA_B/C (`-opt-mul` and `-opt-speed`).
- `MULU.L #2..256,Dn` optimized to `LSL.L #x,Dn` (`-opt-mul`).
- `MVZ.? #x,Dn` and `MVS.? #x,Dn` are optimized to `MOVEQ #x,Dn`.
- `ORI.? #0,<ea>` optimized to `TST.? <ea>`.
- `SUB.? #x,<ea>` optimized to `SUBQ.? #x,<ea>`, when `x` is between 1 and 8.
- `SUB.? #x,<ea>` optimized to `ADDQ.? #x,<ea>`, when `x` is between -1 and -8.
- `SUBA.? #x,An` translated to `LEA (-x,An),An`, when `x` is between -32767 and 32768.

21.7 Known Problems

Some known problems of this module at the moment:

- In some rare cases, mainly by stupid input sources, the optimizer might oscillate forever between two states. When this happens, assembly will be terminated automatically after some time.
- When using `FMOVE` immediate addressing modes, but without specifying a size extension, constants between `$80000000` and `$ffffffff` are stored with 32 bits, which leads to sign-extension problems when the instruction is really 64 or 96 bits.

21.8 Error Messages

This module has the following error messages:

- 2001: instruction not supported on selected architecture
- 2002: illegal addressing mode
- 2003: invalid register list
- 2004: missing `)` in register indirect addressing mode
- 2005: address register required
- 2006: bad size extension
- 2007: displacement at bad position
- 2008: base or index register expected
- 2009: missing `]` in memory indirect addressing mode
- 2010: no extension allowed here
- 2011: illegal scale factor
- 2012: can't scale PC register
- 2013: index register expected
- 2014: too many `]` in memory indirect addressing mode
- 2015: missing outer displacement

- 2016: %c expected
- 2017: can't use PC register as index
- 2018: double registers in list
- 2019: data register required
- 2020: illegal bitfield width/offset
- 2021: constant integer expression required
- 2022: value from -64 to 63 required for k-factor
- 2023: need 32 bits to reference a program label
- 2024: option expected
- 2025: absolute value expected
- 2026: operand value out of range: %ld (valid: %ld..%ld)
- 2027: label in operand required
- 2028: using signed operand as unsigned: %ld (valid: %ld..%ld), %ld to fix
- 2029: branch destination out of range
- 2030: displacement out of range
- 2031: absolute displacement expected
- 2032: unknown option %c%c ignored
- 2033: absolute short address out of range
- 2034: 8-bit branch with zero displacement was converted to 16-bit
- 2035: illegal opcode extension
- 2036: extension for unsized instruction ignored
- 2037: immediate operand out of range
- 2038: immediate operand has illegal type or size
- 2039: data objects with %d bits size are not supported
- 2040: data out of range
- 2041: data has illegal type
- 2042: illegal combination of ColdFire addressing modes
- 2043: FP register required
- 2044: unknown cpu type
- 2045: register expected
- 2046: link.w changed to link.l
- 2047: branch out of range changed to jmp
- 2048: lea-displacement out of range, changed into move/add
- 2049: translated (A%d) into (0,A%d) for movep
- 2050: operand optimized: %s
- 2051: operand translated: %s
- 2051: instruction optimized: %s
- 2053: instruction translated: %s
- 2054: branch optimized into: b<cc>.%c

- 2055: branch translated into: b<cc>.%c
- 2056: basereg A%d already in use
- 2057: basereg A%d is already free
- 2058: short-branch to following instruction turned into a nop
- 2059: not a valid small data register
- 2060: small data mode is not enabled
- 2061: division by zero
- 2062: can't use B%d register as index
- 2063: register list on both sides
- 2064: "%s" directive was replaced by an instruction with the same name
- 2065: Addr.reg. operand at level #0 causes F-line exception
- 2066: Dr and Dq are identical, transforming DIVxL.L effectively into DIVx.L
- 2067: not a valid register list symbol
- 2068: trailing garbage in operand
- 2069: encoding absolute displacement directly
- 2070: internal symbol %s has been modified
- 2071: instruction too large for bank prefix
- 2072: bad FPU id %d for selected cpu type

22 PowerPC cpu module

This chapter documents the Backend for the PowerPC microprocessor family.

22.1 Legal

This module is written in 2002-2016 by Frank Wille and is covered by the vasm copyright without modifications.

22.2 Additional options for this module

This module provides the following additional options:

- `-big` Select big-endian mode.
- `-little` Select little-endian mode.
- `-many` Allow both, 32- and 64-bit instructions.
- `-mavec`, `-maltivec`
 Generate code for the AltiVec unit.
- `-mcom` Allow only common PPC instructions.
- `-m601` Generate code for the PPC 601.
- `-mppc32`, `-mppc`, `-m603`, `-m604`
 Generate code for the 32-bit PowerPC 6xx family.
- `-mppc64`, `-m620`
 Generate code for the 64-bit PowerPC 600 family.
- `-m7400`, `-m7410`, `-m7455`
 Generate code for the 32-bit PowerPC 74xx (G4) family.
- `-m7450` Generate code for the 32-bit PowerPC 7450.
- `-m403`, `-m405`
 Generate code for the IBM/AMCC 32-bit embedded 40x family.
- `-m440`, `-m460`
 Generate code for the AMCC 32-bit embedded 440/460 family.
- `-m821`, `-m850`, `-m860`
 Generate code for the 32-bit MPC8xx PowerQUICC I family.
- `-mbooke` Generate code for the 32-bit Book-E architecture.
- `-me300` Generate code for the 32-bit e300 core (MPC51xx, MPC52xx, MPC83xx).
- `-me500` Generate code for the 32-bit e500 core (MPC85xx), including SPE, EFS and PMR.
- `-mpwr` Generate code for the POWER family.
- `-mpwrx`, `-mpwr2`
 Generate code for the POWER2 family.

-no-regnames

Don't predefine any register-name symbols.

-opt-branch

Enables translation of 16-bit branches into "B<!cc> \$+8 ; B label" sequences when destination is out of range.

-sd2reg=<n>

Sets the 2nd small data base register to Rn.

-sdreg=<n>

Sets small data base register to Rn.

The default setting is to generate code for a 32-bit PPC G2, G3, G4 CPU with AltiVec support.

22.3 General

This backend accepts PowerPC instructions as described in the instruction set manuals from IBM, Motorola, Freescale and AMCC.

The full instruction set of the following families is supported: POWER, POWER2, 40x, 44x, 46x, 60x, 620, 750, 74xx, 860, Book-E, e300 and e500.

The target address type is 32 or 64 bits, depending on the selected CPU model. Floating point constants in instructions and data are supported and encoded in IEEE format.

Default alignment for sections and instructions is 4 bytes. Data is aligned to its natural alignment by default.

22.4 Extensions

This backend provides the following specific extensions:

- When not disabled by the option **-no-regnames**, the registers r0 - r31, f0 - f31, v0 - v31, cr0 - cr7, vrsave, sp, rtoc, fp, fpscr, xer, lr, ctr, and the symbols lt, gt, so and un will be predefined on startup and may be referenced by the program.

This backend extends the selected syntax module by the following directives:

.sdreg <n>

Sets the small data base register to Rn.

.sd2reg <n>

Sets the 2nd small data base register to Rn.

22.5 Optimizations

This backend performs the following optimizations:

- 16-bit branches, where the destination is out of range, are translated into B<!cc> \$+8 and a 26-bit unconditional branch.

22.6 Known Problems

Some known problems of this module at the moment:

- No real differentiation between 403, 750, 860 instructions at the moment.
- There may still be some unsupported PPC models.

22.7 Error Messages

This module has the following error messages:

- 2002: instruction not supported on selected architecture
- 2003: constant integer expression required
- 2004: trailing garbage in operand
- 2005: illegal operand type
- 2006: missing closing parenthesis in load/store addressing mode
- 2007: relocation does not allow hi/lo modifier
- 2008: multiple relocation attributes
- 2009: multiple hi/lo modifiers
- 2010: data size %d not supported
- 2011: data has illegal type
- 2012: relocation attribute not supported by operand
- 2013: operand out of range: %ld (allowed: %ld to %ld)
- 2014: not a valid register (0-31)
- 2015: missing base register in load/store addressing mode
- 2016: missing mandatory operand
- 2017: ignoring fake operand

23 c16x/st10 cpu module

This chapter documents the Backend for the c16x/st10 microcontroller family.

Note that this module is not yet fully completed!

23.1 Legal

This module is written in 2002-2004 by Volker Barthelmann and is covered by the vasm copyright without modifications.

23.2 Additional options for this module

This module provides the following additional options:

-no-translations

Do not translate between jump instructions. If the offset of a **jmp** instruction is too large, it will not be translated to **jmps** but an error will be emitted.

Also, **jmpa** will not be optimized to **jmp**.

The pseudo-instruction **jmp** will still be translated.

-jmpa A **jmp** or **jmp** instruction that is translated due to its offset being larger than 8 bits will be translated to a **jmpa** rather than a **jmps**, if possible.

23.3 General

This backend accepts c16x/st10 instructions as described in the Infineon instruction set manuals.

The target address type is 32bit.

Default alignment for sections and instructions is 2 bytes.

23.4 Extensions

This backend provides the following specific extensions:

- There is a pseudo instruction **jmp** that will be translated either to a **jmp** or **jmpa** instruction, depending on the offset.
- The **sfr** pseudo opcode can be used to declare special function registers. It has two, three or four arguments. The first argument is the identifier to be declared as special function register. The second argument is either the 16bit sfr address or its 8bit base address (0xfe for normal sfrs and 0xf0 for extended special function registers). In the latter case, the third argument is the 8bit sfr number. If another argument is given, it specifies the bit-number in the sfr (i.e. the declaration declares a single bit).

Example:

```
.sfr    zeros,0xfe,0x8e
```

- **SEG** and **SOF** can be used to obtain the segment or segment offset of a full address.

Example:

```
mov r3,#SEG farfunc
```

23.5 Optimizations

This backend performs the following optimizations:

- `jmp` is translated to `jmp`, if possible. Also, if `-no-translations` was not specified, `jmp` and `jmpa` are translated.
- Relative jump instructions with an offset that does not fit into 8 bits are translated to a `jmp` instruction or an inverted jump around a `jmp` instruction.
- For instruction that have two forms `gpr,#IMM3/4` and `reg,#IMM16` the smaller form is used, if possible.

23.6 Known Problems

Some known problems of this module at the moment:

- Lots...

23.7 Error Messages

This module has the following error messages:

- 2001: illegal operand
- 2002: word register expected
- 2004: value does not find in %d bits
- 2005: data size not supported
- 2006: illegal use of SOF
- 2007: illegal use of SEG
- 2008: illegal use of DPP prefix

24 6502 cpu module

This chapter documents the backend for the MOS/Rockwell 6502 microprocessor family. It also supports the Rockwell/WDC 65C02, the Hudson Soft HuC6280 and the WDC 65802/65816 instruction sets.

24.1 Legal

This module is written in 2002,2006,2008-2012,2014-2023 by Frank Wille and is covered by the vasm copyright without modifications.

24.2 Additional options for this module

This module provides the following additional options:

- 6280** Recognize all HuC6280 instructions.
- 802** Same as **-816**. There is no difference in the instruction set.
- 816** Enables the 8/16 bit instruction set for the WDC65816/65802 and additional directives to switch loading of the accumulator and/or the index register between 8 and 16 bits. The target address size is 24 bits.
- bbcade** Swap meaning of < and > unary operators for compatibility with the BBC ADE assembler.
- c02** Recognize all 65C02 instructions. This excludes DTV (**-dtv**) and illegal (**-illegal**) instructions.
- ce02** Enables the Commodore CSG65CE02 instruction set, which extends on the WDC02 instruction set.
- dtv** Recognize the three additional C64-DTV instructions.
- illegal** Allow 'illegal' 6502 instructions to be recognized.
- mega65** Enables the 45GS02 instruction set for the MEGA65 computer.
- opt-branch**
 Enables translation of B<cc> branches into sequences of B<!cc> *+5 ; JMP label when necessary. BRA (DTV, 65C02) is directly translated into a JMP when out of range. It also performs optimization of JMP to BRA, whenever possible.
- wdc02** Recognize all 65C02 instructions and the WDC65C02 extensions (RMB,SMB,BBR,BBS,STP,WAI).

24.3 General

This backend accepts 6502 family instructions as described in the instruction set reference manuals from MOS and Rockwell, which are valid for the following CPUs: 6502 - 6518, 6570, 6571, 6702, 7501, 8500, 8502.

Optionally accepts 65C02 family instructions as described in the instruction set reference manuals from Rockwell and WDC. Also supports the WDC extensions in the W65C02 and W65C134.

Optionally accepts 65CE02 family instructions as described in the instruction set reference manuals from Commodore Semiconductor Group.

Optionally accepts HuC6280 instructions as described in the instruction set reference manuals from Hudson Soft.

Optionally accepts 45GS02 instructions as defined by the Mega65 project.

Optionally accepts WDC65816 instructions as described in the Programming Manual by The Western Design Center.

The target address type is 16 bits, or 24 bits in WDC65816 mode.

Instructions consist of one up to three bytes for the standard 6502 family (up to 7 bytes for the 6280) and require no alignment. There is also no alignment requirement for sections and data.

All known mnemonics for illegal instructions are optionally recognized (e.g. `dcm` and `dcp` refer to the same instruction). Some illegal instructions (e.g. `$ab`) are known to show unpredictable behaviour, or do not always work the same on different CPUs.

Note that the WDC65816 `MVN` and `MVP` block move instructions require a full 24-bit address (or a label) for the source and destination, as documented in WDC's Programming Manual. This assembler additionally allows to specify the bank byte directly, which is triggered by a constant value between 0 and 255.

24.4 Extensions

This backend provides the following specific extensions:

- The parser understands a lo/hi-modifier to select low- or high-byte of a 16-bit word. The character `<` is used to select the low-byte and `>` for the high-byte. It has to be the first character before an expression. See also option `-bbcade`. In WDC65816 mode the character `^` can be used to select the bank-byte (bits 16 to 23) of a full 24 bit address.
- When applying the operation `>>8`, `/256`, `%256` or `&256` on a label, an appropriate lo/hi-byte relocation will automatically be generated.
- The hi/lo-modifier can also be used in front of absolute addressing modes, to enforce absolute 16-bit addressing (hi/`>`) or zero/direct-page 8-bit addressing (lo/`<`). In WDC65816 mode the `>` character selects full 24-bit addressing instead, and `!` or `|` may be used to enforce 16-bit addressing.

This backend extends the selected syntax module by the following directives:

`<symbol> ezp <expr>`

Works exactly like the `equ` directive, but marks `<symbol>` as a zero page symbol and use zero page addressing whenever `<symbol>` is used in a memory addressing mode.

a8 Declares that immediate instructions loading the accumulator read 8 bits (default, WDC65816 only).

a16 Declares that immediate instructions loading the accumulator read 16 bits (WDC65816 only).

setdp <expr>	Set the current base address of the zero/direct page for optimizations from absolute to zero-page addressing modes. Example: set it to \$2000 for the HuC6280/PC-Engine.
x8	Declares that immediate instructions loading the index registers read 8 bits (default, WDC65816 only).
x16	Declares that immediate instructions loading the index registers read 16 bits (WDC65816 only).
zero	Switch to a zero page section called zero or .zero , which has the type bss with attributes " aurw ". Accesses to symbols from this section will default to zero page addressing mode.
zpage <symbol1> [, <symbol2>...]	Mark symbols as zero page and use zero page addressing for expressions based on this symbol, unless overridden by a hi-modifier (>).

All these directives are also available in the form starting with a dot (.).

24.5 Optimizations

This backend performs the following operand optimizations and translations:

- Absolute addressing modes are optimized to zero-page (or direct-page) addressing modes, whenever possible.
- An absolute addressing mode will be promoted to long addressing (24 bits) for the WDC65816, when needed.
- Conditional branches, where the destination is out of range, are translated into **B<!cc> *+5** and an absolute **JMP** instruction (**-opt-branch**).
- Some CPUs also allow optimization of **JMP** to **BRA**, when **-opt-branch** was given.

24.6 Known Problems

Some known problems of this module at the moment:

- None?

24.7 Error Messages

This module has the following error messages:

- 2001: instruction not supported on selected architecture
- 2002: trailing garbage in operand
- 2003: addressing mode selector ignored
- 2004: data size %d not supported
- 2005: relocation does not allow hi/lo modifier
- 2006: operand doesn't fit into %d bits
- 2007: branch destination out of range
- 2008: illegal bit number

- 2009: identifier expected
- 2010: multiple hi/lo modifiers
- 2011: zero/direct-page addressing not available
- 2012: operand not in zero/direct-page range
- 2013: absolute-long addressing not available

25 ARM cpu module

This chapter documents the backend for the Advanced RISC Machine (ARM) microprocessor family.

25.1 Legal

This module is written in 2004,2006,2010-2015 by Frank Wille and is covered by the vasm copyright without modifications.

25.2 Additional options for this module

This module provides the following additional options:

- `-a2` Generate code compatible with ARM V2 architecture.
- `-a3` Generate code compatible with ARM V3 architecture.
- `-a3m` Generate code compatible with ARM V3m architecture.
- `-a4` Generate code compatible with ARM V4 architecture.
- `-a4t` Generate code compatible with ARM V4t architecture.
- `-big` Output big-endian code and data.
- `-little` Output little-endian code and data (default).
- `-m2` Generate code for the ARM2 CPU.
- `-m250` Generate code for the ARM250 CPU.
- `-m3` Generate code for the ARM3 CPU.
- `-m6` Generate code for the ARM6 CPU.
- `-m600` Generate code for the ARM600 CPU.
- `-m610` Generate code for the ARM610 CPU.
- `-m7` Generate code for the ARM7 CPU.
- `-m710` Generate code for the ARM710 CPU.
- `-m7500` Generate code for the ARM7500 CPU.
- `-m7d` Generate code for the ARM7d CPU.
- `-m7di` Generate code for the ARM7di CPU.
- `-m7dm` Generate code for the ARM7dm CPU.
- `-m7dmi` Generate code for the ARM7dmi CPU.
- `-m7tdmi` Generate code for the ARM7tdmi CPU.
- `-m8` Generate code for the ARM8 CPU.
- `-m810` Generate code for the ARM810 CPU.
- `-m9` Generate code for the ARM9 CPU.

- `-m9` Generate code for the ARM9 CPU.
- `-m920` Generate code for the ARM920 CPU.
- `-m920t` Generate code for the ARM920t CPU.
- `-m9tdmi` Generate code for the ARM9tdmi CPU.
- `-msa1` Generate code for the SA1 CPU.
- `-mstrongarm`
 Generate code for the STRONGARM CPU.
- `-mstrongarm110`
 Generate code for the STRONGARM110 CPU.
- `-mstrongarm1100`
 Generate code for the STRONGARM1100 CPU.
- `-opt-adr` The `ADR` directive will be automatically converted into `ADRL` if required (which inserts an additional `ADD/SUB` to calculate an address).
- `-opt-ldrpc`
 The maximum range in which PC-relative symbols can be accessed through `LDR` and `STR` is extended from $\pm 4\text{KB}$ to $\pm 1\text{MB}$ (or ± 256 Bytes to ± 65536 Bytes when accessing half-words). This is done by automatically inserting an additional `ADD` or `SUB` instruction before the `LDR/STR`.
- `-thumb` Start assembling in Thumb mode.

25.3 General

This backend accepts ARM instructions as described in various ARM CPU data sheets. Additionally some architectures support a second, more dense, instruction set, called THUMB. There are special directives to switch between these two instruction sets.

The target address type is 32bit.

Default alignment for instructions is 4 bytes for ARM and 2 bytes for THUMB. Sections will be aligned to 4 bytes by default. Data is aligned to its natural alignment by default.

25.4 Extensions

This backend extends the selected syntax module by the following directives:

- `.arm` Generate 32-bit ARM code.
- `.thumb` Generate 16-bit THUMB code.

25.5 Optimizations

This backend performs the following optimizations and translations for the ARM instruction set:

- `LDR/STR Rd,symbol`, with a distance between symbol and PC larger than 4KB, is translated to `ADD/SUB Rd,PC,#offset&0xff000 + LDR/STR Rd,[Rd,#offset&0xff]`, when allowed by the option `-opt-ldrpc`.

- `ADR Rd,symbol` is translated to `ADD/SUB Rd,PC,#rotated_offset8`.
- `ADRL Rd,symbol` is translated to `ADD/SUB Rd,PC,#hi_rotated8 + ADD/SUB Rd,Rd,#lo_rotated8`. `ADR` will be automatically treated as `ADRL` when required and when allowed by the option `-opt-adr`.
- The immediate operand of ALU-instructions will be translated into the appropriate 8-bit-rotated value. When rotation alone doesn't succeed the backed will try it with inverted and negated values (inverting/negating the ALU-instruction too). Optionally you may specify the rotate constant yourself, as an additional operand.

For the THUMB instruction set the following optimizations and translations are done:

- A conditional branch with a branch-destination being out of range is translated into `B<!cc> .+4 + B label`.
- The `BL` instruction is translated into two sub-instructions combining the high- and low 22 bit of the branch displacement.

25.6 Known Problems

Some known problems of this module at the moment:

- Only instruction sets up to ARM architecture V4t are supported.

25.7 Error Messages

This module has the following error messages:

- 2001: instruction not supported on selected architecture
- 2002: trailing garbage in operand
- 2003: label from current section required
- 2004: branch offset (%ld) is out of range
- 2005: PC-relative load/store (offset %ld) out of range
- 2006: cannot make rotated immediate from PC-relative offset (0x%lx)
- 2007: constant integer expression required
- 2008: constant (0x%lx) not suitable for 8-bit rotated immediate
- 2009: branch to an unaligned address (offset %ld)
- 2010: not a valid ARM register
- 2011: PC (r15) not allowed in this mode
- 2012: PC (r15) not allowed for offset register Rm
- 2013: PC (r15) not allowed with write-back
- 2014: register r%ld was used multiple times
- 2015: illegal immediate shift count (%ld)
- 2016: not a valid shift register
- 2017: 24-bit unsigned immediate expected
- 2018: data size %d not supported
- 2019: illegal addressing mode: %s
- 2020: signed/halfword ldr/str doesn't support shifts

- 2021: %d-bit immediate offset out of range (%ld)
- 2022: post-indexed addressing mode expected
- 2023: operation not allowed on external symbols
- 2024: ldc/stc offset has to be a multiple of 4
- 2025: illegal coprocessor operation mode or type: %ld\n
- 2026: %d-bit unsigned immediate offset out of range (%ld)
- 2027: offset has to be a multiple of %d
- 2028: instruction at unaligned address
- 2029: TSTP/TEQP/CMNP/CMPP deprecated on 32-bit architectures
- 2030: rotate constant must be an even number between 0 and 30: %ld
- 2031: %d-bit unsigned constant required: %ld

26 80x86 cpu module

This chapter documents the Backend for the 80x86 microprocessor family.

26.1 Legal

This module is written in 2005-2006,2011,2015-2016 by Frank Wille and is covered by the vasm copyright without modifications.

26.2 Additional options for this module

This module provides the following additional options:

<code>-cpudebug=<n></code>	Enables debugging output.
<code>-m8086</code>	Generate code for the 8086 CPU.
<code>-mi186</code>	Generate code for the 80186 CPU.
<code>-mi286</code>	Generate code for the 80286 CPU.
<code>-mi386</code>	Generate code for the 80386 CPU.
<code>-mi486</code>	Generate code for the 80486 CPU.
<code>-mi586</code>	Generate code for the Pentium.
<code>-mi686</code>	Generate code for the PentiumPro.
<code>-mpentium</code>	Generate code for the Pentium.
<code>-mpentiumpro</code>	Generate code for the PentiumPro.
<code>-mk6</code>	Generate code for the AMD K6.
<code>-mathlon</code>	Generate code for the AMD Athlon.
<code>-msledgehammer</code>	Generate code for the Sledgehammer CPU.
<code>-m64</code>	Generate code for 64-bit architectures (x86_64).

26.3 General

This backend accepts 80x86 instructions as described in the Intel Architecture Software Developer's Manual.

The target address type is 32 bits. It is 64 bits when the x86_64 architecture was selected (-m64). Floating point constants in instructions and data are supported and encoded in IEEE format.

Instructions do not need any alignment. Data is aligned to its natural alignment by default. The backend uses AT&T-syntax! This means the left operands are always the source and the right operand is the destination. Register names have to be prefixed by a '%'.

The operation size is indicated by a 'b', 'w', 'l', etc. suffix directly appended to the mnemonic. The assembler can also determine the operation size from the size of the registers being used.

26.4 Extensions

Predefined register symbols in this backend:

- 8-bit registers: `al cl dl bl ah ch dh bh axl cxl dxl spl bpl sil dil r8b r9b r10b r11b r12b r13b r14b r15b`
- 16-bit registers: `ax cx dx bx sp bp si di r8w r9w r10w r11w r12w r13w r14w r15w`
- 32-bit registers: `eax ecx edx ebx esp ebp esi edi r8d r9d r10d r11d r12d r13d r14d r15d`
- 64-bit registers: `rax rcx rdx rbx rsp ebp rsi rdi r8 r9 r10 r11 r12 r13 r14 r15`
- segment registers: `es cs ss ds fs gs`
- control registers: `cr0 cr1 cr2 cr3 cr4 cr5 cr6 cr7 cr8 cr9 cr10 cr11 cr12 cr13 cr14 cr15`
- debug registers: `dr0 dr1 dr2 dr3 dr4 dr5 dr6 dr7 dr8 dr9 dr10 dr11 dr12 dr13 dr14 dr15`
- test registers: `tr0 tr1 tr2 tr3 tr4 tr5 tr6 tr7`
- MMX and SIMD registers: `mm0 mm1 mm2 mm3 mm4 mm5 mm6 mm7 xmm0 xmm1 xmm2 xmm3 xmm4 xmm5 xmm6 xmm7 xmm8 xmm9 xmm10 xmm11 xmm12 xmm13 xmm14 xmm15`
- FPU registers: `st st(0) st(1) st(2) st(3) st(4) st(5) st(6) st(7)`

This backend extends the selected syntax module by the following directives:

- `.code16` Sets the assembler to 16-bit addressing mode.
- `.code32` Sets the assembler to 32-bit addressing mode, which is the default.
- `.code64` Sets the assembler to 64-bit addressing mode.

26.5 Optimizations

This backend performs the following optimizations:

- Immediate operands are optimized to the smallest size which can still represent the absolute value.
- Displacement operands are optimized to the smallest size which can still represent the absolute value.
- Jump instructions are optimized to 8-bit displacements, when possible.

26.6 Known Problems

Some known problems of this module at the moment:

- 64-bit operations are incomplete and experimental.

26.7 Error Messages

This module has the following error messages:

- 2001: instruction not supported on selected architecture
- 2002: trailing garbage in operand
- 2003: same type of prefix used twice
- 2004: immediate operand illegal with absolute jump
- 2005: base register expected
- 2006: scale factor without index register
- 2007: missing ')' in baseindex addressing mode
- 2008: redundant %s prefix ignored
- 2009: unknown register specified
- 2010: using register %%%s instead of %%%s due to '%c' suffix
- 2011: %%%s not allowed with '%c' suffix
- 2012: illegal suffix '%c'
- 2013: instruction has no suffix and no register operands - size is unknown
- 2015: memory operand expected
- 2016: you cannot pop %%%s
- 2017: translating to %s %%%s, %%%s
- 2018: translating to %s %%%s
- 2019: absolute scale factor required
- 2020: illegal scale factor (valid: 1,2,4,8)
- 2021: data objects with %d bits size are not supported
- 2022: need at least %d bits for a relocatable symbol
- 2023: pc-relative jump destination out of range (%lld)
- 2024: instruction doesn't support these operand sizes
- 2025: cannot determine immediate operand size without a suffix
- 2026: displacement doesn't fit into %d bits

27 z80 cpu module

This chapter documents the backend for the 8080/z80/gbz80/64180/RCMx000 microprocessor family.

27.1 Legal

This module is copyright in 2009 by Dominic Morris.

```
* Redistribution and use in source and binary forms, with or without
* modification, are permitted provided that the following conditions
* are met:
* 1. Redistributions of source code must retain the above copyright
*   notice, this list of conditions and the following disclaimer.
* 2. Redistributions in binary form must reproduce the above copyright
*   notice, this list of conditions and the following disclaimer in the
*   documentation and/or other materials provided with the distribution.
*
* THIS SOFTWARE IS PROVIDED BY THE AUTHOR ‘‘AS IS’’ AND ANY EXPRESS OR
* IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES
* OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED.
* IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT,
* INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
* NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
* DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
* THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
* (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF
* THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

27.2 Additional options for this module

This module provides the following additional options:

- 8080 Turns on 8080/8085 compatibility mode. Any use of z80 (or higher) opcodes will result in an error being generated.
- gbz80 Turns on gbz80 compatibility mode. Any use of non-supported opcodes will result in an error being generated.
- hd64180 Turns on 64180 mode supporting additional 64180 opcodes.
- intel-syntax
 - Turns on the older Intel 8080 syntax mode. When this mode is activated, mnemonics and operand types from the Intel 8080 syntax instead of the Zilog Z80 syntax (such as `STA 1234h` instead of `ld (1234h),a`) will be valid. This option can be used in parallel with `-8080` to use both sets of mnemonics, although this is discouraged, as two instructions (`jp` and `cp`) mean different things in each syntax. In this case, these instructions will be assembled as the Intel syntax, and a warning will be emitted.
- rcm2000

- `-rcm3000`
- `-rcm4000` Turns on Rabbit compatibility mode, generating the correct codes for moved opcodes and supporting the additional Rabbit instructions. In this mode, 8 bit access to the 16 bit index registers is not permitted.
- `-rcmemu` Turns on emulation of some instructions which aren't available on the Rabbit processors.
- `-swapixiy` Swaps the usage of ix and iy registers. This is useful for compiling generic code that uses an index register that is reserved on the target machine.
- `-z80asm` Switches on z80asm mode. This translates ASMPc to \$ and accepts some pseudo opcodes that z80asm supports. Most emulation of z80asm directives is provided by the oldsyntax syntax module.

27.3 General

This backend accepts z80 family instructions in standard Zilog syntax. Rabbit opcodes are accepted as defined in the publicly available reference material from Rabbit Semiconductor, with the exception that the `ljp` and `lcall` opcodes need to be supplied with a 24 bit number rather than an 8 bit `xpc` and a 16 bit address.

The target address type is 16 bit.

Instructions consist of one up to six bytes and require no alignment. There is also no alignment requirement for sections and data.

27.4 Extensions

This backend provides the following specific extensions:

- Certain Rabbit opcodes can be prefixed by the `altd` and/or the `ioi/ioe` modifier. For details of which instructions these are valid for please see the documentation from Rabbit.
- The parser understands a `lo/hi`-modifier to select low- or high-byte of a 16-bit word. The character `<` is used to select the low-byte and `>` for the high-byte. It has to be the first character before an expression.
- When applying the operation `/256`, `%256` or `&256` on a label, an appropriate `lo/hi`-byte relocation will automatically be generated.

27.5 Optimisations

This backend supports the emulation of certain z80 instructions on the Rabbit/gbz80 processor. These instructions are `rld`, `rrd`, `cpi`, `cpir`, `cpd` and `cpdr`. The link stage should provide routines with the opcode name prefixed with `rcmx_` (eg `rcmx_rld`) which implements the same functionality. Example implementations are available within the z88dk CVS tree.

Additionally, for the Rabbit targets the missing call `cc`, opcodes will be emulated.

27.6 Known Problems

Some known problems of this module at the moment:

- Not all RCM4000 opcodes are supported (`llcall`, `lljp` are not available).

27.7 Error Messages

This module has the following error messages:

- 2001: trailing garbage in operand
- 2002: Opcode not supported by %s (%s)
- 2003: Index registers not available on 8080
- 2004: out of range for 8 bit expression (%d)
- 2005: invalid bit number (%d) should be in range 0..7
- 2006: rst value out of range (%d/0x%02x)
- 2007: %s value out of range (%d)
- 2008: index offset should be a constant
- 2009: invalid branch type for jr
- 2010: Rabbit target doesn't support rst %d
- 2011: Rabbit target doesn't support 8 bit index registers
- 2012: z180 target doesn't support 8 bit index registers
- 2013: invalid branch type for jre
- 2014: Opcode not supported by %s (%s) but it can be emulated (-rcmemu)
- 2015: %s specifier is only valid for Rabbit processors
- 2016: Only one of ioi and ioe can be specified at a time
- 2017: %s specifier is not valid for the opcode %s
- 2018: %s specifier redundant for the opcode %s
- 2019: %s specifier has no effect on the opcode %s
- 2020: Operand value must evaluate to a constant for opcode %s
- 2021: Unhandled operand type wanted 0x%x got 0x%x
- 2022: Missed matched index registers on %s
- 2023: Only out (c),0 is supported for the opcode %s
- 2024: Operations between different index registers are forbidden
- 2025: Operations between ix/iy/hl are forbidden
- 2026: Double indirection forbidden
- 2027: Instruction %s will be assembled as '%s'
- 2028: index offset out of bounds (%d)

28 6800 cpu module

This chapter documents the backend for the Motorola 6800 microprocessor family.

28.1 Legal

This module is written in 2013-2016,2021 by Esben Norby and Frank Wille and is covered by the vasm copyright without modifications.

28.2 Additional options for this module

This module provides the following additional options:

- m6800 Generate code for the 6800 CPU (default setting).
- m6801 Generate code for the 6801 CPU.
- m68hc11 Generate code for the 68HC11 CPU.

28.3 General

This backend accepts 6800 family instructions for the following CPUs:

- 6800 code generation: 6800, 6802, 6808.
- 6801 code generation: 6801, 6803.
- 68HC11.

The 6804, 6805 and 68HC08 are not supported, they use a similar instruction set, but are not opcode compatible.

The target address type is 16 bit.

Instructions consist of one up to five bytes and require no alignment. There is also no alignment requirement for sections and data.

28.4 Extensions

This backend provides the following specific extensions:

- When an instruction supports direct and extended addressing mode the < character can be used to force direct mode and the > character forces extended mode. Otherwise the assembler selects the best mode automatically, which defaults to extended mode for external symbols.
- When applying the operation /256, %256 or &256 on a label, an appropriate lo/hi-byte relocation will automatically be generated.

28.5 Optimizations

None.

28.6 Known Problems

Some known problems of this module at the moment:

- None?

28.7 Error Messages

This module has the following error messages:

- 2001: trailing garbage in operand
- 2002: data size %d not supported
- 2003: operand doesn't fit into 8-bits
- 2004: branch destination out of range

29 6809/6309/68HC12 cpu module

This chapter documents the backend for the Motorola 6809, 68HC12 and Hitachi 6309.

29.1 Legal

This module is written in 2020-2021 by Frank Wille and is covered by the vasm copyright without modifications.

29.2 Additional options for this module

This module provides the following additional options:

- 6809 Generate code for the 6809 CPU (default setting). Also works on the 6309, which is backwards compatible.
- 6309 Generate code for the 6309 CPU.
- 68hc12 Generate code for the 68HC12 CPU.
- opt-branch
 Translate short-branches to long and optimize long-branches to short when required/possible. Also tries to optimize `jmp` and `jsr` instructions into short-branches.
- opt-offset
 Delete zero offsets in indexed addressing modes, when possible.
- opt-pc Convert all extended addressing modes with local or external labels to indexed, PC-relative addressing. Also translates absolute `jmp/jsr` instructions into PC-relative `lbra/lbsr` (or better).

29.3 General

This backend accepts 6809/6309 instructions as described in the Motorola 6809 and Hitachi 6309 Programmer's Reference (Copyright 2009 Darren Atkinson). Optionally supports the 68HC12 instruction set as documented in Motorola's CPU12 Reference Manual.

The target address type is 16 bit.

Instructions consist of one up to six bytes and require no alignment. There is also no alignment requirement for sections and data.

29.4 Extensions

The backend supports the unary operators `<` and `>` to either select the size of an addressing mode or the LSB/MSB of a 16-bit word.

- When direct or extended addressing modes are applicable, `<` enforces direct mode and `>` enforces extended mode.
- For indexed, PC-relative addressing modes `<` enforces an 8-bit offset, while `>` enforces a 16-bit offset.
- For all other indexed addressing modes with a constant offset `<` enforces an 8-bit offset and `>` enforces a 16-bit offset.

- For immediate addressing modes or data constants < selects the LSB of a word and > selects the MSB.
- When applying the operation /256, %256 or &256 on a label in immediate addressing modes or data constants, an appropriate lo/hi-byte relocation will automatically be generated.

In absence of < or > vasm selects the best addressing mode possible, i.e. the one which requires the least amount of memory when the symbol value is known, or the one which allows the largest symbol values, when it is unknown at assembly time.

This backend extends the selected syntax module by the following directives:

setdp <expr>

Set the current base address of the direct page. It is used to decide whether an extended addressing mode can be optimized to direct addressing. No effect for 68HC12.

direct <symbol>

Tell the assembler to use direct addressing for expressions based on this symbol.

29.5 Optimizations

This backend performs the following operand optimizations:

- Short-branches (Bcc) are optionally translated into long-branches (LBcc) when their destination is undefined, in a different section or out of range. Note that there is no LBSR on the HC12.
- Long-branches (LBcc) are optionally optimized into short-branches (Bcc) when possible.
- Optionally optimize JMP into BRA and JSR into BSR when possible (same section, distance representable in 8 bits).
- Optionally translate JMP into LBRA and JSR into LBSR (`-opt-pc`).
- Optionally translate all extended addressing, referring to local or external labels, to an indexed, PC-relative addressing mode (`-opt-pc`).
- Optionally optimize indexed addressing modes with a constant zero offset into a no-offset addressing mode, which executes faster. Not possible on the HC12.
- Always select the shortest indexed addressing mode for constant offsets, unless externally defined.

29.6 Known Problems

Some known problems of this module at the moment:

- PC-relative addressing modes in MOVx instructions may be wrong. Needs testing.

29.7 Error Messages

This module has the following error messages:

- 2001: trailing garbage in operand
- 2002:] expected for indirect addressing mode
- 2003: missing valid index register

- 2004: pc-relative offset out of range: %ld
- 2005: constant offset out of range: %ld
- 2006: bad auto decrement/increment value: %d
- 2007: indirect addressing not allowed
- 2008: auto increment/decrement not allowed
- 2009: short branch out of range: %ld
- 2010: long branch out of range: %ld
- 2011: decrement branch out of range: %ld
- 2012: data size %d not supported
- 2013: data expression doesn't fit into %d bits
- 2014: illegal bit number specification: %d
- 2015: omitted offset taken as 5-bit zero offset
- 2016: immediate expression doesn't fit into %d bits
- 2017: directive ignored as selected CPU has no DP register
- 2018: double size modifier ignored
- 2019: addressing mode not supported

30 Jaguar RISC cpu module

This chapter documents the backend for the Atari Jaguar GPU/DSP RISC processor.

30.1 Legal

This module is written in 2014-2017,2020,2021 by Frank Wille and is covered by the vasm copyright without modifications.

30.2 Additional options for this module

This module provides the following additional options:

- `-big` Output big-endian code and data (default).
- `-little` Output little-endian code and data.
- `-many` Generate code for GPU or DSP RISC. All instructions are accepted (default).
- `-mdsp`
- `-mjerry` Generate code for the DSP RISC (part of Jerry).
- `-mgpu`
- `-mtom` Generate code for the GPU RISC (part of Tom).

30.3 General

This backend accepts RISC instructions for the GPU or DSP in Atari's Jaguar custom chip set according to the "Jaguar Technical Reference Manual for Tom & Jerry", Revision 8. Documentation bugs were fixed by using various sources on the net.

The target address type is 32 bits.

Default alignment for instructions is 2 bytes. Data is aligned to its natural alignment by default.

30.4 Optimizations

This backend performs the following optimizations and translations for the GPU/DSP RISC instruction set:

- `load (Rn+0),Rm` is optimized to `load (Rn),Rm`.
- `store Rn,(Rm+0)` is optimized to `store Rn,(Rm)`.

30.5 Extensions

This backend extends the selected syntax module by the following directives (note that a leading dot is optional):

`<symbol> ccdef <expression>`

Allows defining a symbol for the condition codes used in `jump` and `jr` instructions. Must be constant number in the range of 0 to 31 or another condition code symbol.

ccundef <symbol>
 Undefine a condition code symbol previously defined via **ccdef**.

dsp Select DSP instruction set.

<symbol> **equr** <Rn>
 Define a new symbol named <symbol> and assign the address register **Rn** to it.
 <Rn> may also be another register symbol. Note that a register symbol must
 be defined before it can be used.

equrundef <symbol>
 Undefine a register symbol previously defined via **equr**.

gpu Select GPU instruction set.

<symbol> **regequ** <Rn>
 Equivalent to **equr**.

regundef <symbol>
 Undefine a register symbol previously defined via **regequ**.

All directives may be optionally preceded by a dot (.), for compatibility with various syntax modules.

30.6 Known Problems

Some known problems of this module at the moment:

- Encoding of **MOVEI** instruction in little-endian mode is unknown.
- The developer has to provide the necessary **NOP** instructions after jumps, or **OR** instructions to work around hardware bugs, her/himself.

30.7 Error Messages

This module has the following error messages:

- 2001: data size %d not supported
- 2002: value from %ld to %ld required

31 PDP11 cpu module

This chapter documents the backend for the PDP-11 CPU architecture.

31.1 Legal

This module is written in 2020 by Frank Wille and is covered by the vasm copyright without modifications.

31.2 Additional options for this module

This module provides the following additional options:

- eis** Enables the Extended Instruction Set option (EIS).
- fis** Enables the Floating point Instruction Set option (FIS).
- msp** Enables additional memory space instructions.
- opt-branch**
 Enables optimization of `jmp` instructions to `br` when possible and translates `br` instructions to `jmp` when required. It will also translate conditional branches, where the destination is out of range, into a `jmp` instruction and a negated conditional branch over this `jmp`.

31.3 General

This backend accepts PDP-11 instructions as described in the PDP11/40 Processor Handbook, by Digital Equipment Corporation.

The target address type is 16 bit.

Instructions consist of two up to six bytes and required 16-bit alignment. Data, when not accessed as single bytes, also requires 16-bit alignment.

31.4 Known Problems

Some known problems of this module at the moment:

- Doesn't support all PDP-11 extensions.

31.5 Error Messages

This module has the following error messages:

- 2001: bad addressing mode
- 2002: bad register
- 2003: pc-relative destination out of range: %ld (valid: %d..%d)
- 2004: bad trap code %ld (valid: %d..%d)
- 2005: displacement out of range: %ld
- 2006: immediate value out of range: %ld
- 2007: absolute address out of range: %ld
- 2008: data size %d not supported
- 2009: data expression doesn't fit into %d bits

32 Trillek TR3200 cpu module

This chapter documents the Backend for the TR3200 cpu.

32.1 Legal

This module is written in 2014 by Luis Panadero Guardeno and is covered by the vasm copyright without modifications.

32.2 General

This backend accepts TR3200 instructions as described in the TR3200 specification (<https://github.com/trillek-team/trillek-computer>)

The target address type is 32 bits.

Default alignment for sections is 4 bytes. Instructions alignment is 4 bytes. Data is aligned to its natural alignment by default, i.e. 2 byte wide data alignment is 2 bytes and 4 byte wide data alignment is 4 bytes.

The backend uses TR3200 syntax! This means the left operands are always the destination and the right operand is the source (except for single operand instructions). Register names have to be prefixed by a '%' (%bp, %r0, etc.) This means that it should accept WaveAsm assembly files if oldstyle syntax module is being used. The instructions are lowercase, -dotdir option is being used and directives are not in the first column.

32.3 Extensions

Predefined register symbols in this backend:

- register by number: r0 r1 r2 r3 r4 r5 r6 r7 r8 r9 r10 r11 r12 r13 r14 r15
- special registers by name: bp sp y ia flags

32.4 Known Problems

Some known problems of this module at the moment:

- This module need to be fully checked, but has been tested building a full program that could be found here : <https://github.com/Zardoz89/trillek-firmware>
- Instruction relocations are missing.

32.5 Error Messages

This module has the following error messages:

- 2001: illegal operand
- 2002: illegal qualifier <%s>
- 2003: data size not supported

32.6 Example

It follows a little example to illustrate TR3200 assembly using the oldstyle syntax module (option `-dotdir` required):

```

const    .equ 0xBEBACAFE          ; A constant
an_addr  .equ 0x100                ; Other constant

; ROM code
        .org 0x100000
        .text
_start  ; Label with or without a ending ":"
        mov %sp, 0x1000            ; Set the initial stack

        mov %r0, 0
        mov %r1, 0xA5
        mov %r2, 0
        storeb %r0, an_addr, %r1

        add %r0, %r2, %bp
        add %r0, %r2, 0
        add %r0, %r0, 10
        add %r0, %r0, 10h
        add %r0, %r0, 0x100010
        add %r0, %r0, (256 + 100) ; vasm parses math expressions

        mov %r2, 0
        mov %r3, 0x10200

        loadb %r6, 0x100200
        loadb %r1, %r2, 0x100200
        loadb %r1, %r2, %r3
        loadb %r4, var1

        push %r0
        .repeat 2                  ; directives to repeat stuff!
        push const
        .endrepeat

        .repeat 2
        pop %r5
        .endrepeat
        pop %r0

        rcall foo                  ; Relative call/jump!
        sleep

foo:    ; Subroutine

```

```
    ifneq %r5, 0
        mul %r5, %r5, 2
        sub %r5, %r5, 1

    ret

; ROM data
    .org 0x100500
var1  .db 0x20                ; A byte size variable
    .even                    ; Enforce to align to even address
var3  .dw 0x1020              ; A word size variable
var4  .dd 0x0A0B0C20          ; A double word size variable
str1  .ascii "Hello world!"   ; ASCII string with null termination
str2  .string "Hello world!"  ; ASCII string with null termination
    .fill 5, 0xFF             ; Fill 5 bytes with 0xFF
    .reserve 5                ; Reserves space for 5 byte
```


33 Interface

33.1 Introduction

This chapter is under construction!

This chapter describes some of the internals of `vasm` and tries to explain what has to be done to write a cpu module, a syntax module or an output module for `vasm`. However if someone wants to write one, I suggest to contact me first, so that it can be integrated into the source tree.

Note that this documentation may mention explicit values when introducing symbolic constants. This is due to copying and pasting from the source code. These values may not be up to date and in some cases can be overridden. Therefore do never use the absolute values but rather the symbolic representations.

33.2 Building vasm

This section deals with the steps necessary to build the typical `vasm` executable from the sources.

33.2.1 Directory Structure

The `vasm`-directory contains the following important files and directories:

`vasm/` The main directory containing the assembler sources.

`vasm/Makefile`
 The Makefile used to build `vasm`.

`vasm/syntax/<syntax-module>/`
 Directories for the syntax modules.

`vasm/cpus/<cpu-module>/`
 Directories for the cpu modules.

`vasm/obj/`
 Directory the object modules will be stored in.

All compiling is done from the main directory and the executables will be placed there as well. The main assembler for a combination of `<cpu>` and `<syntax>` will be called `vasm<cpu>_<syntax>`. All output modules are usually integrated in every executable and can be selected at runtime. Otherwise you have to adapt the `OUTFMTS` definition in `make.rules` and select those you want.

33.2.2 Adapting the Makefile

Before building anything you have to insert correct values for your compiler and operating system in the `Makefile`.

TARGET Here you may define an extension which is appended to the executable's name. Useful, if you build various targets in the same directory.

TARGETEXTENSION

Defines the file name extension for executable files. Not needed for most operating systems. For Windows it would be `.exe`.

CC Here you have to insert a command that invokes an ANSI C compiler you want to use to build vasm. It must support the `-I` option in the same way like e.g. `vc` or `gcc`.

COPTS Here you will usually define an option like `-c` to instruct the compiler to generate an object file. Additional options, like the optimization level, should also be inserted here as well. Specifying the host OS helps to determine work-directories for DWARF and defines the appropriate internal symbol for the host's file system path style. The following are supported:

-DAMIGA AmigaOS (M68k or PPC), MorphOS, AROS. Defines the internal symbol `__AMIGAFS`.

-DATARI Atari TOS. Defines the internal symbol `__MSDOSFS`.

-DMSDOS CP/M, MS-DOS, Windows. Defines the internal symbol `__MSDOSFS`.

-DUNIX All kinds of Unix (Linux, BSD) including MacOSX and Atari-MiNT. Defines the internal symbol `__UNIXFS`.

-D_WIN32 Windows. Defines the internal symbol `__MSDOSFS`.

Building without specifying a host-OS is allowed. Then vasm defaults to Unix-style path handling and will not define a file system symbol for conditional assembly. Other options:

-DLOWMEM Builds for a host-OS with a low amount of memory. This will basically reduce all hash tables to minimal size.

CCOUT Here you define the option which is used to specify the name of an output file, which is usually `-o`.

LD Here you insert a command which starts the linker. This may be the the same as under **CC**.

LDFLAGS Here you have to add options which are necessary for linking. E.g. some compilers need special libraries for floating-point.

LDOUT Here you define the option which is used by the linker to specify the output file name.

RM Specify a command to delete a file, e.g. `rm -f`.

An example for the Amiga using `vbcc` would be:

```
TARGET = _os3
TARGETEXTENSION =
CC = vc +aos68k
CCOUT = -o
COPTS = -c -c99 -cpu=68020 -DAMIGA -O1
LD = $(CC)
```



```
LDOUT = $(CCOUT)
LDFLAGS = -lmieee
RM = delete force quiet
```

An example for a typical Unix-installation would be:

```
TARGET =
TARGETEXTENSION =
CC = gcc
CCOUT = -o
COPTS = -c -O2
LD = $(CC)
LDOUT = $(CCOUT)
LDFLAGS = -lm
RM = rm -f
```

Open/Net/Free/Any BSD systems will probably require an additional `-D_ANSI_SOURCE` in `COPTS`.

33.2.3 Building vasm

Note to users of BSD systems: You will probably have to use GNU make instead of BSD make, i.e. in the following examples replace "make" with "gmake".

Type:

```
make CPU=<cpu> SYNTAX=<syntax>
```

For example:

```
make CPU=ppc SYNTAX=std
```

The following CPU modules can be selected:

- CPU=6502
- CPU=6800
- CPU=6809
- CPU=arm
- CPU=c16x
- CPU=jagrisc
- CPU=m68k
- CPU=pdp11
- CPU=ppc
- CPU=qnice
- CPU=test
- CPU=tr3200
- CPU=vidcore
- CPU=x86
- CPU=z80

The following syntax modules can be selected:

- SYNTAX=std

- SYNTAX=mot
- SYNTAX=madmac
- SYNTAX=oldstyle
- SYNTAX=test

For Windows and various Amiga targets there are already Makefiles included, which you may either copy on top of the default Makefile, or call it explicitly with `make's -f` option:

```
make -f Makefile.OS4 CPU=ppc SYNTAX=std
```

33.3 vasm global variables

Important global variables, which may be read or modified by `syntax-`, `cpu-` or `output-` modules.

```
char *inname;
```

Input source file name.

```
char *outname;
```

Output source file name.

```
int exec_out;
```

Non-zero, when the output file is an executable and not an object file.

```
source *cur_src;
```

Pointer to the current source text instance (see structures below).

```
char *defsectname;
```

Name of a default section which vasm creates when a label or code occurs in the source without any preceding `section` or `org` directive. Assigning NULL means that the default is an absolute section and its base address is taken from `defsectorg`.

```
char *defsecttype;
```

Attributes of the default section (see above). May be NULL to indicate that no default has been defined and vasm will show an error.

```
taddr defsectorg;
```

Used when `defsectname==NULL`. Defines the base address of a default absolute `org` section.

```
char emptystr[];
```

An empty string (zero length).

33.4 General data structures

This section describes the fundamental data structures used in vasm which are usually necessary to understand for writing any kind of module (`cpu`, `syntax` or `output`). More detailed information is given in the respective sections on writing specific modules where necessary.

33.4.1 Source

A source structure represents a source text module, which can be either the main source text, an included file or a macro. There is always a link to the parent source from where the current source context was included or called.

struct source *parent;

Pointer to the parent source context. Assembly continues there when the current source context ends.

int parent_line;

Line number in the parent source context, from where we were called. This information is needed, because line numbers are only reliable during parsing and later from the atoms. But an include directive doesn't create an atom.

struct source_file *srcfile;

The **source_file** structure has the unique file name, index and text-pointer for this source text instance. Used for debugging output, like DWARF.

char *name;

File name of the main source or include file, or macro name.

char *text;

Pointer to the source text start.

size_t size;

Size of the source text to assemble in bytes.

struct source *defsrc;

This is a NULL-pointer for real source text files. Otherwise it is a reference to the source which defines the current macro or repetition.

int defline;

Valid when **defsrc** is not NULL. Contains the starting line number of a macro or repetition in a source text file.

macro *macro;

Pointer to macro structure, when currently inside a macro (see also **num_params**).

unsigned long repeat;

Number of repetitions of this source text. Usually this is 1, but for text blocks between a **rept** and **endr** directive it allows any number of repetitions, which is decremented every time the end of this source text block is reached.

char *irpname;

Name of the iterator symbol in special repeat loops which use a sequence of arbitrary values, being assigned to this symbol within the loop. Example: **irp** directive in **std-syntax**.

struct macarg *irpvals;

A list of arbitrary values to iterate over in a loop. With each iteration the frontmost value is removed from the list until it is empty.

`int cond_level;`
 Current level of conditional nesting while entering this source text. It is automatically restored to the previous level when leaving the source prematurely through `end_source()`.

`struct macarg *argnames;`
 The current list of named macro arguments.

`int num_params;`
 Number of macro parameters passed at the invocation point from the parent source. For normal source files this entry will be -1. For macros 0 (no parameters) or higher.

`char *param[MAXMACPARAMS];`
 Pointer to the macro parameters.

`int param_len[MAXMACPARAMS];`
 Number of characters per macro parameter.

`int num_qual;`
 (If `MAX_QUALIFIERS!=0.`) Number of qualifiers for a macro. when not passed on invocation these are the default qualifiers.

`char *qual[MAX_QUALIFIERS];`
 (If `MAX_QUALIFIERS!=0.`) Pointer to macro qualifiers.

`int qual_len[MAX_QUALIFIERS];`
 (If `MAX_QUALIFIERS!=0.`) Number of characters per macro qualifier.

`unsigned long id;`
 Every source has its unique id. Useful for macros supporting the special `\@` parameter.

`char *srcptr;`
 The current source text pointer, pointing to the beginning of the next line to assemble.

`int line;` Line number in the current source context. After parsing the line number of the current atom is stored here.

`size_t bufsize;`
 Current size of the line buffer (`linebuf`). The size of the line buffer is extended automatically, when an overflow happens.

`char *linebuf;`
 A buffer for the current line being assembled in this source text. A child-source, like a macro, can refer to arguments from this buffer, so every source has got its own. When returning to the parent source, the `linebuf` is deallocated to save memory.

`expr *cargexp;`
 (If `CARGSYM` was defined.) Pointer to the current expression assigned to the `CARG`-symbol (used to select a macro argument) in this source instance. So it can be restored when reentering this instance.

`long reptn;`

(If `REPTNSYM` was defined.) Current value of the repetition counter symbol in this source instance. So it can be restored when reentering this instance.

33.4.2 Sections

One of the top level structures is a linked list of sections describing continuous blocks of memory. A section is specified by an object of type `section` with the following members that can be accessed by the modules:

`struct section *next;`

A pointer to the next section in the list.

`char *name;`

The name of the section.

`char *attr;`

A string describing the section flags in ELF notation (see, for example, documentation of the `.section` directive of the standard syntax module.

`atom *first;`

`atom *last;`

Pointers to the first and last atom of the section. See following sections for information on atoms.

`taddr align;`

Alignment of the section in bytes.

`uint32_t flags;`

Flags of the section. Currently available flags are:

HAS_SYMBOLS

At least one symbol is defined in this section.

RESOLVE_WARN

The current atom changed its size multiple times, so `atom_size()` is now called with this flag set in its section to make the back-end (e.g. `instruction_size()`) aware of it and do less aggressive optimizations.

UNALLOCATED

Section is unallocated, which means it doesn't use any memory space in the output file. Such a section will be removed before creating the output file and all its labels converted into absolute expression symbols. Used for "offset" sections. Refer to `switch_offset_section()`.

LABELS_ARE_LOCAL

As long as this flag is set new labels in a section are defined as local labels, with the section name as global parent label.

ABSOLUTE Section is loaded at an absolute address in memory.

PREVABS Remembers state of the **ABSOLUTE** flag before entering relocated-org mode (`IN_RORG`). So it can be restored later.

IN_RORG Section has entered relocated-org mode, which also sets the **ABSOLUTE** flag. In this mode code is written into the current section, but relocated to an absolute address. No relocation information are generated.

NEAR_ADDRESSING

Section is marked as suitable for cpu-specific "near" addressing modes. For example, base-register relative or zero/direct-page. The cpu backend can use this information as an optimization hint when referencing symbols from this section.

FAR_ADDRESSING

Section requires cpu-specific "far" addressing modes. For example an addressing mode including the bank or "segment". The cpu backend may use this information to select appropriate addressing modes when referencing symbols from this section.

taddr org;

Start address of a section. Usually zero.

taddr pc; Current address in this section. Can be used while traversing through the section. Has to be updated by a module using it. Is set to **org** at the beginning.

unsigned long idx;

A member usable by the output module for private purposes.

33.4.3 Symbols

Symbols are represented by a linked list of type **symbol** with the following members that can be accessed by the modules:

int type; Type of the symbol. Available are:

#define LABSYM 1

The symbol is a label defined at a specific location.

#define IMPORT 2

The symbol is externally defined.

#define EXPRESSION 3

The symbol is defined using an expression.

uint32_t flags;

Flags of this symbol. Available are:

#define TYPE_UNKNOWN 0

The symbol has no type information.

#define TYPE_OBJECT 1

The symbol defines an object.

#define TYPE_FUNCTION 2

The symbol defines a function.

#define TYPE_SECTION 3

The symbol defines a section.

```
#define TYPE_FILE 4
    The symbol defines a file.

#define EXPORT (1<<3)
    The symbol is exported to other object files.

#define INEVAL (1<<4)
    Used internally.

#define COMMON (1<<5)
    The symbol is a common symbol.

#define WEAK (1<<6)
    The symbol is weak, which means the linker may overwrite it with
    any global definition of the same name. Weak symbols may also
    stay undefined, in which case the linker would assign them a value
    of zero.

#define LOCAL (1<<7)
    Only informational. A symbol can be explicitly declared as local
    by a syntax-module directive.

#define VASMINTERN (1<<8)
    Vasm-internal symbol, which is usually not exported into an object
    file.

#define PROTECTED (1<<9)
    Used internally to protect the current-PC symbol from deletion.

#define REFERENCED (1<<10)
    Symbol was referenced in the source and a relocation entry has
    been created.

#define ABSLABEL (1<<11)
    Label was defined inside an absolute section, or during relocated-
    org mode. So it has an absolute address and will not generate a
    relocation entry when being referenced.

#define EQUATE (1<<12)
    Symbols flagged as EQUATE are constant and its value must not be
    changed.

#define REGLIST (1<<13)
    Symbol is a register list definition.

#define USED (1<<14)
    Symbol appeared in an expression. Symbols which were only de-
    fined, (as label or equate) and never used throughout the whole
    source, don't get this flag set.

#define NEAR (1<<15)
    Symbol may be referenced by "near" addressing mode. For exam-
    ple, base register relative. Used as an optimization hint in the cpu
    backend.
```

```
#define XDEF (1<<16)
```

This symbol must become defined in the source. Which means its **type** must not remain **IMPORT**. Otherwise a warning is displayed.

```
#define XREF (1<<17)
```

Symbol is externally defined and its **type** must never become something else than **IMPORT**. Otherwise an error is displayed.

```
#define RSRVD_S (1L<<24)
```

The range from bit 24 to 27 (counted from the LSB) is reserved for use by the syntax module.

```
#define RSRVD_O (1L<<28)
```

The range from bit 28 to 31 (counted from the LSB) is reserved for use by the output module.

The type-flags can be extracted using the **TYPE()** macro which expects a pointer to a symbol as argument.

```
char *name;
```

The name of the symbol.

```
expr *expr;
```

The expression in case of **EXPRESSION** symbols.

```
expr *size;
```

The size of the symbol, if specified.

```
section *sec;
```

The section a **LABSYM** symbol is defined in.

```
taddr pc;
```

The address of a **LABSYM** symbol.

```
taddr align;
```

The alignment of the symbol in bytes.

```
unsigned long idx;
```

A member usable by the output module for private purposes.

33.4.4 Register symbols

Optional register symbols are available when the backend defines **HAVE_REGSYMS** in **cpu.h** together with the hash table size. Example:

```
#define HAVE_REGSYMS
```

```
#define REGSYMHTSIZE 256
```

A register symbol is defined by an object of type **regsym** with the following members that can be accessed by the modules:

```
char *reg_name;
```

Symbol name.

```
int reg_type;
```

Optional type of register.

```
unsigned int reg_flags;
```

Optional register symbol flags.


```
unsigned int reg_num;
    Register number or value.
```

Refer to `symbol.h` for functions to create and find register symbols.

33.4.5 Atoms

The contents of each section are a linked list built out of non-separable atoms. The general structure of an atom is:

```
struct atom {
    struct atom *next;
    int type;
    taddr align;
    taddr lastsize;
    unsigned changes;
    source *src;
    int line;
    listing *list;
    union {
        instruction *inst;
        dblock *db;
        symbol *label;
        sblock *sb;
        defblock *defb;
        void *opts;
        int srcline;
        char *ptext;
        printexpr *pexpr;
        expr *roffs;
        taddr *rorg;
        assertion *assert;
        aoutnlist *nlist;
    } content;
};
```

The members have the following meaning:

```
struct atom *next;
    Pointer to the following atom (NULL if last).
```

```
int type; The type of the atom. Can be one of
```

```
#define VASMDEBUG 0
    Used for internal debugging.
```

```
#define LABEL 1
    A label is defined here.
```

```
#define DATA 2
    Some data bytes of fixed length and constant data are put here.
```

#define INSTRUCTION 3

Generally refers to a machine instruction or pseudo/opcode. These atoms can change length during optimization passes and will be translated to **DATA**-atoms later.

#define SPACE 4

Defines a block of data filled with one value of a given size (up to **MAXBYTES** bytes). BSS sections usually contain only such atoms, but they are also sometimes useful as shorter versions of **DATA**-atoms in other sections.

#define DATADEF 5

Defines data of fixed size which can contain cpu specific operands and expressions. Usually generated by data in a source text, which are no machine instructions. Will be translated to **DATA**-atoms later.

#define LINE 6

A source text line number (usually from a high level language) is bound to the atom's address. Useful for source level debugging in certain ABIs.

#define OPTS 7

A means to change assembler options at a specific source text line. For example optimization settings, or the cpu type to generate code for. The cpu backend has to define **HAVE_CPU_OPTS** and export the required functions if it wants to use this type of atom.

#define PRINTTEXT 8

A string is printed to stdout during the final assembler pass. A newline is automatically appended.

#define PRINTEXPR 9

Prints the value of an expression during the final assembler pass to stdout.

#define ROFFS 10

Set the program counter to an address relative to the section's start address. These atoms will be translated into **SPACE** atoms in the final pass.

#define RORG 11

Assemble this block under the given base address, while the code is still written into the original memory region.

#define RORGEND 12

Ends a **RORG** block and returns to the original addressing.

#define ASSERT 13

The assertion expression is checked in the final pass and an error message is generated (using the expression string and an optional message out of this atom) when it evaluates to 0.

```
#define NLIST 14
```

Defines a stab-entry for the a.out object file format. nlist-style stabs can also occur embedded in other object file formats, like ELF.

```
taddr align;
```

The alignment of this atom. Address must be dividable by `align`.

```
taddr lastsize;
```

The size of this atom in the last resolver pass. When the size has changed in the current pass, the assembler will request another resolver run through the section.

```
unsigned changes;
```

Number of changes in the size of this atom since pass number `FASTOPTPHASE`. An increasing number usually indicates a problem in the cpu backend's optimizer and will be flagged by setting `RESOLVE_WARN` in the Section flags, as soon as `changes` exceeds `MAXSIZECHANGES`. So the backend can choose not to optimize this atom as aggressive as before.

```
source *src;
```

Pointer to the source text object to which this atom belongs.

```
int line; The source line number that created this atom.
```

```
listing *list;
```

Pointer to the listing file object to which this atom belongs.

```
instruction *inst;
```

(In union `content`.) Pointer to an instruction structure in the case of an `INSTRUCTION`-atom. Contains the following elements:

```
int code; The cpu specific code of this instruction.
```

```
char *qualifiers[MAX_QUALIFIERS];
```

(If `MAX_QUALIFIERS!=0`.) Pointer to the qualifiers of this instruction.

```
operand *op[MAX_OPERANDS];
```

(If `MAX_OPERANDS!=0`.) The cpu-specific operands of this instruction.

```
instruction_ext ext;
```

(If the cpu backend defines `HAVE_INSTRUCTION_EXTENSION`.) A cpu-specific structure. Typically used to store appropriate opcodes, allowed addressing modes, supported cpu derivatives etc.

```
dblock *db;
```

(In union `content`.) Pointer to a `dblock` structure in the case of a `DATA`-atom. Contains the following elements:

```
taddr size;
```

The number of bytes stored in this atom.

```
char *data;
```

A pointer to the data.

```

    rlist *relocs;
        A pointer to relocation information for the data.

symbol *label;
    (In union content.) Pointer to a symbol structure in the case of a LABEL-atom.

sblock *sb;
    (In union content.) Pointer to a sblock structure in the case of a SPACE-atom.
    Contains the following elements:

    size_t space;
        The number of space-elements (see below) to generate here.

    expr *space_exp;
        The above size as an expression, which will be evaluated during
        assembly and copied to space in the final pass.

    size_t size;
        The size of each space-element and of the fill-pattern in bytes.

    unsigned char fill[MAXBYTES];
        The fill pattern, up to MAXBYTES bytes.

    expr *fill_exp;
        Optional. Evaluated and copied to fill in the final pass, when not
        null.

    rlist *relocs;
        A pointer to relocation information for the space.

    taddr maxalignbytes;
        An optional number of maximum padding bytes to fulfil the atom's
        alignment requirement. Zero means there is no restriction.

    uint32_t flags;
        SPC_UNINITIALIZED
            This space is completely uninitialized. May be used as
            a hint by output modules.

        SPC_DATABSS
            The output module should not allocate any file space
            for this atom, when possible (example: DataBss sec-
            tion, as supported by the "hunkexe" output file for-
            mat). It is not needed to set this flag when the output
            section is BSS.

defblock *defb;
    (In union content.) Pointer to a defblock structure in the case of a DATADEF-
    atom. Contains the following elements:

    taddr bitsize;
        The size of the definition in bits.

    operand *op;
        Pointer to a cpu-specific operand structure.

```

```

void *opts;
    (In union content.) Points to a cpu-backend specific options object in the case
    of a OPTS-atom.

int srcline;
    (In union content.) Line number for source level debugging in the case of a
    LINE-atom.

char *ptext;
    (In union content.) A string to print to stdout in case of a PRINTTEXT-atom.

printexpr *pexpr;
    (In union content.) Pointer to a printexpr structure in the case of a PRINTEXPR-
    atom. Contains the following elements:

    expr *print_exp;
        Pointer to an expression to evaluate and print.

    short type;
        Format type of the printed value. We can print as hexadecimal
        (PEXP_HEX), signed decimal (PEXP_SDEC), unsigned decimal (PEXP_
        UDEC), binary (PEXP_BIN) OR ASCII (PEXP_ASC).

    short size;
        Size (precision) of the printed value in bits. Excessive bits will be
        masked out, and sign-extended when requested.

expr *roffs;
    (In union content.) The expression holds the relative section offset to align to
    in case of a ROFFS-atom.

taddr *rorg;
    (In union content.) Assemble the code under the base address in rorg in case
    of a RORG-atom.

assertion *assert;
    (In union content.) Pointer to an assertion structure in the case of an ASSERT-
    atom. Contains the following elements:

    expr *assert_exp;
        Pointer to an expression which should evaluate to non-zero.

    char *exprstr;
        Pointer to the expression as text (to be used in the output).

    char *msgstr;
        Pointer to the message, which would be printed when assert_exp
        evaluates to zero.

aoutnlist *nlist;
    (In union content.) Pointer to an nlist structure, describing an aout stab entry,
    in case of an NLIST-atom. Contains the following elements:

    char *name;
        Name of the stab symbol.

```

```

int type; Symbol type. Refer to stabs.h for definitions.

int other;
    Defines the nature of the symbol (function, object, etc.).

int desc; Debugger information.

expr *value;
    Symbol's value.

```

33.4.6 Relocations

DATA and SPACE atoms can have a relocation list attached that describes how this data must be modified when linking/relocating. They always refer to the data in this atom only.

There are a number of predefined standard relocations and it is possible to add other cpu-specific relocations. Note however, that it is always preferable to use standard relocations, if possible. Chances that an output module supports a certain relocation are much higher if it is a standard relocation.

A relocation list uses this structure:

```

typedef struct rlist {
    struct rlist *next;
    void *reloc;
    int type;
} rlist;

```

Type identifies the relocation type. All the standard relocations have type numbers between `FIRST_STANDARD_RELOC` and `LAST_STANDARD_RELOC`. Consider `reloc.h` to see which standard relocations are available.

The detailed information can be accessed via the pointer `reloc`. It will point to a structure that depends on the relocation type, so a module must only use it if it knows the relocation type.

All standard relocations point to a type `nreloc` structure with the following members:

```

size_t byteoffset;
    Offset in bytes, from the start of the current DATA atom, to the beginning of the
    relocation field. This may also be the address which is used as a basis for PC-
    relative relocations. Or a common basis for several separated relocation fields,
    which will be translated into a single relocation type by the output module.

```

```

size_t bitoffset;
    Offset in bits to the beginning of the relocation field, adds to
    byteoffset*bitsperbyte. Bits are counted in a bit-stream from lower to
    higher address bytes. But note, that inside a little-endian byte they are
    counted from the LSB to the MSB, while they are counted from the MSB to
    the LSB for big-endian targets.

```

```

int size; The size of the relocation field in bits.

```

```

taddr mask;
    The mask defines which portion of the relocated value is set by this relocation
    field.

```

`taddr addend;`

Value to be added to the symbol value.

`symbol *sym;`

The symbol referred by this relocation

To describe the meaning of these entries, we will define the steps that shall be executed when performing a relocation:

1. Extract the `size` bits from the data atom, starting with bit number `byteoffset*bitsperbyte+bitoffset`. We start counting bits from the lowest to the highest numbered byte in memory. Inside a big-endian byte we count from the MSB to the LSB. Inside a little-endian byte we count from the LSB to the MSB.
2. Determine the relocation value of the symbol. For a simple absolute relocation, this will be the value of the symbol `sym` plus the `addend`. For other relocation types, more complex calculations will be needed. For example, in a program-counter relative relocation, the value will be obtained by subtracting the address of the data atom plus `byteoffset` from the value of `sym` plus `addend`.
3. Calculate the bit-wise "and" of the value obtained in the step above and the `mask` value.
4. Normalize, i.e. shift the value above right as many bit positions as there are low order zero bits in `mask`.
5. Add this value to the value extracted in step 1.
6. Insert the low order `size` bits of this value into the data atom starting with bit `byteoffset*bitsperbyte+bitoffset`.

33.4.7 Errors

Each module can provide a list of possible error messages contained e.g. in `syntax_errors.h` or `cpu_errors.h`. They are a comma-separated list of a printf-format string and error flags. Allowed flags are `WARNING`, `ERROR`, `FATAL`, `MESSAGE` and `NOLINE`. They can be combined using or (`|`). `NOLINE` has to be set for error messages during initialization or while writing the output, when no source text is available. Errors cause the assembler to return false. `FATAL` causes the assembler to terminate immediately.

The errors can be emitted using the function `syntax_error(int n,...)`, `cpu_error(int n,...)` or `output_error(int n,...)`. The first argument is the number of the error message (starting from zero). Additional arguments must be passed according to the format string of the corresponding error message.

33.5 Syntax modules

A new syntax module must have its own subdirectory under `vasm/syntax`. At least the files `syntax.h`, `syntax.c` and `syntax_errors.h` must be written.

33.5.1 The file `syntax.h`

```
#define ISIDSTART(x)/ISIDCHAR(x)
```

These macros should return non-zero if and only if the argument is a valid character to start an identifier or a valid character inside an identifier, respectively. `ISIDCHAR` must be a superset of `ISIDSTART`.

#define ISBADID(p,l)
Even with **ISIDSTART** and **ISIDCHAR** checked, there may be combinations of characters which do not form a valid initializer (for example, a single character). This macro returns non-zero, when this is the case. First argument is a pointer to the new identifier and second is its length.

#define ISEOL(x)
This macro returns true when the string pointing at **x** is either a comment character or end-of-line.

#define CHKIDEND(s,e) chkidend((s),(e))
Defines an optional function to be called at the end of the identifier recognition process. It allows you to adjust the length of the identifier by returning a modified **e**. Default is to return **e**. The function is defined as **char *chkidend(char *startpos, char *endpos)**.

#define BOOLEAN(x) -(x)
Defines the result of boolean operations. Usually this is **(x)**, as in C, or **-(x)** to return -1 for True.

#define NARGSYM "NARG"
Defines the name of an optional symbol which contains the number of arguments in a macro.

#define CARGSYM "CARG"
Defines the name of an optional symbol which can be used to select a specific macro argument with **\.**, **\+** and **\-**.

#define REPTNSYM "REPTN"
Defines the name of an optional symbol containing the counter of the current repeat iteration.

#define EXPSKIP() s=exp_skip(s)
Defines an optional replacement for **skip()** to be used in **expr.c**, to skip blanks in an expression. Useful to forbid blanks in an expression and to ignore the rest of the line (e.g. to treat the rest as comment). The function is defined as **char *exp_skip(char *stream)**.

#define IGNORE_FIRST_EXTRA_OP 1
Should be defined as non-zero (true) when the syntax module wants to ignore the operand field on instructions without an operand. Useful, when everything following an operand should be regarded as comment, without a comment character.

#define MAXMACPARAMS 35
Optionally defines the maximum number of macro arguments, if you need more than the default number of 9.

#define SKIP_MACRO_ARGNAME(p) skip_identifier(p)
An optional function to skip a named macro argument in the macro definition. Argument is the current source stream pointer. The default is to skip an identifier.


```
#define MACRO_ARG_OPTS(m,n,a,p) NULL
```

An optional function to parse and skip options, default values and qualifiers for each macro argument. Returns `NULL` when no argument options have been found. Arguments are:

```
struct macro *m;
```

Pointer to the macro structure being currently defined.

```
int n;
```

Argument index, starting with zero.

```
char *a;
```

Name of this argument.

```
char *p;
```

Current source stream pointer. An updated pointer will be returned.

Defaults to unused.

```
#define MACRO_ARG_SEP(p) (*p==',' ? skip(p+1) : NULL)
```

An optional function to skip a separator between the macro argument names in the macro definition. Returns `NULL` when no valid separator is found. Argument is the current source stream pointer. Defaults to using comma as the only valid separator.

```
#define MACRO_PARAM_SEP(p) (*p==',' ? skip(p+1) : NULL)
```

An optional function to skip a separator between the macro parameters in a macro call. Returns `NULL` when no valid separator is found. Argument is the current source stream pointer. Defaults to using comma as the only valid separator.

```
#define EXEC_MACRO(s)
```

An optional function to be called just before a macro starts execution. Parameters and qualifiers are already parsed. Argument is the `source` pointer of the new macro. Defaults to unused.

33.5.2 The file `syntax.c`

A syntax module has to provide the following elements (all other functions should be `static` to prevent name clashes):

```
const char *syntax_copyright;
```

A string that will be emitted as part of the copyright message.

```
hashtable *dirhash;
```

A pointer to the hash table with all directives.

```
char commentchar;
```

A character used to introduce a comment until the end of the line.

```
int dotdirs;
```

Define `dotdirs` as non-zero, when the syntax module works with directives starting with a dot (`.`).

```
int init_syntax(void);
```

Will be called during startup, after argument parsing. Must return zero if initializations failed, non-zero otherwise.

```
int syntax_args(char *);
```

This function will be called with the command line arguments (unless they were already recognized by other modules). If an argument was recognized, return non-zero.

```
int syntax_defsect(void);
```

Lets the syntax module define a default section, which is used when no section was created by any `section` or `org` directive before the first code or data is defined. May set `defsectname`, `defsecttype` and `defsectorg` accordingly and return with non-zero. Or return with zero and accept the defaults, which are: `defsectname=".text"` and `defsecttype="acrx"`.

```
char *skip(char *);
```

A function to skip whitespace etc.

```
void eol(char *);
```

This function should check that the argument points to the end of a line (only comments or whitespace following). If not, an error or warning message should be omitted.

```
char *const_prefix(char *,int *);
```

Check if the first argument points to the start of a constant. If yes return a pointer to the real start of the number (i.e. skip a prefix that may indicate the base) and write the base of the number through the pointer passed as second argument. Return zero if it does not point to a number.

```
char *const_suffix(char *,char *);
```

First argument points to the start of the constant (including prefix) and the second argument to first character after the constant (excluding suffix). Checks for a constant-suffix and skips it. Return pointer to the first character after that constant. Example: constants with a 'h' suffix to indicate a hexadecimal base.

```
void parse(void);
```

This is the main parsing function. It has to read lines via the `read_next_line()` function, parse them and create sections, atoms and symbols. Pseudo directives are usually handled by the syntax module. Instructions can be parsed by the cpu module using `parse_instruction()`.

```
char *parse_macro_arg(struct macro *,char *,struct namelen *,struct namelen *);
```

Called to parse a macro parameter by using the source stream pointer in the second argument. The start pointer and length of a single passed parameter is written to the first `struct namelen`, while the optionally selected named macro argument is passed in the second `struct namelen`. When the `len` field of the second `namelen` is zero, then the argument is selected by position instead by name. Returns the updated source stream pointer after successful parsing.

```
int expand_macro(source *,char **,char *,int);
```

Expand parameters and special commands inside a macro source. The second argument is a pointer to the current source stream pointer, which is updated

on any successful expansion. The function will return the number of characters written to the destination buffer (third argument) in this case. Returning -1 means: no expansion took place. The last argument defines the space in characters which is left in the destination buffer.

```
char *get_local_label(char **);
```

Gets a pointer to the current source pointer. Has to check if a valid local label is found at this point. If yes return a pointer to the vasm-internal symbol name representing the local label and update the current source pointer to point behind the label.

Have a look at the support functions provided by the frontend to help.

33.6 CPU modules

A new cpu module must have its own subdirectory under `vasm/cpus`. At least the files `cpu.h`, `cpu.c` and `cpu_errors.h` must be written.

33.6.1 The file `cpu.h`

A cpu module has to provide the following elements (all other functions should be `static` to prevent name clashes) in `cpu.h`:

```
#define MAX_OPERANDS 3
```

Maximum number of operands of one instruction.

```
#define MAX_QUALIFIERS 0
```

Maximum number of mnemonic-qualifiers per mnemonic.

```
#define NO_MACRO_QUALIFIERS
```

Define this, when qualifiers shouldn't be allowed for macros. For some architectures, like ARM, macro qualifiers make no sense.

```
typedef int32_t taddr;
```

Data type to represent a target-address. Preferably use the types from `stdint.h`. Does not necessarily have to match the cpu's address bus size (refer to `bytespertaddr`), but the largest data you will be able to do calculations with. For example, you may want to allow 32-bit data definitions for an 8-bit cpu.

```
typedef uint32_t utaddr;
```

Unsigned data type to represent a target-address.

```
#define LITTLEENDIAN 1
```

```
#define BIGENDIAN 0
```

Define these according to the target endianness. For CPUs which support big- and little-endian, you may assign a global variable here. So be aware of it, and never use `#if BIGENDIAN`, but always `if (BIGENDIAN)` in your code.

```
#define VASM_CPU_<cpu> 1
```

Defines a cpu-specific macro. May be used to perform special handling in syntax- or output-modules.

```
#define INST_ALIGN 2
```

Minimum instruction alignment.

```
#define DATA_ALIGN(n) ...
    Default alignment for n-bit data. Can also be a function.

#define DATA_OPERAND(n) ...
    Operand class for n-bit data definitions. Can also be a function. Negative
    values denote a floating point data definition of -n bits.

typedef ... operand;
    Structure to store an operand for a machine instruction or a data constant.

typedef ... mnemonic_extension;
    Mnemonic extension for the cpu's instruction table.
```

Optional features, which can be enabled by defining the following macros:

```
#define FLOAT_PARSER 1
    Enables the floating point parser and floating point evaluation in the
    expression module. With this option the backend has to be prepared that
    expressions may contain floating point constants, which can be checked
    by testing the result of type_of_expr(expression) for FLT. Then use
    eval_expr_float(expression,&float_val) to retrieve the floating point
    value with type tfloat. It is up to the backend to convert the host's floating
    point format, which should be IEEE, into the backend's native format. The
    vasm frontend only supports IEEE to IEEE conversion via conv2ieee32()
    and conv2ieee64().

#define HAVE_INSTRUCTION_EXTENSION 1
    If cpu-specific data should be added to all instruction atoms.

typedef ... instruction_ext;
    Type for the above extension.

#define CLEAR_OPERANDS_ON_START 1
    Backend requires zeroed operand structures when calling parse_operand() for
    the first time. Might be useful to parse operands only once. Defaults to unde-
    fined.

#define CLEAR_OPERANDS_ON_MNEMO 1
    Backend requires zeroed operand structures when calling parse_operand() for
    any new mnemonic. Useful to parse the same operand multiple times on the
    current mnemonic, but reset everything for the next mnemonic. Defaults to
    undefined.

START_PARENTH(x)
    Valid opening parenthesis for instruction operands. Defaults to '('.

END_PARENTH(x)
    Valid closing parenthesis for instruction operands. Defaults to ')'.

#define MNEMONIC_VALID(i)
    An optional function with the arguments (int idx). Returns true when the
    mnemonic with index idx is valid for the current state of the backend (e.g. it
    is available for the selected cpu architecture).
```

```
#define MNEMOHTABSIZE 0x4000
```

You can optionally overwrite the default hash table size defined in `vasm.h`. May be necessary for larger mnemonic tables.

```
#define OPERAND_OPTIONAL(p,t)
```

When defined, this is a function with the arguments (`operand *op, int type`), which returns true when the given operand type (`type`) is optional. The function is only called for missing operands and should also initialize `op` with default values (e.g. 0).

Implementing additional target-specific unary operations is done by defining the following optional macros:

```
#define EXT_UNARY_NAME(s)
```

Should return True when the string in `s` points to an operation name we want to handle.

```
#define EXT_UNARY_TYPE(s)
```

Returns the operation type code for the string in `s`. Note that the last valid standard operation is defined as `LAST_EXP_TYPE`, so the target-specific types will start with `LAST_EXP_TYPE+1`.

```
#define EXT_UNARY_EVAL(t,v,r,c)
```

Defines a function with the arguments (`int t, taddr v, taddr *r, int c`) to handle the operation type `t` returning an `int` to indicate whether this type has been handled or not. Your operation will be applied on the value `v` and the result is stored in `*r`. The flag `c` is passed as 1 when the value is constant (no relocatable addresses involved).

```
#define EXT_FIND_BASE(b,e,s,p)
```

Defines a function with the arguments (`symbol **b, expr *e, section *s, taddr p`) to save a pointer to the base symbol of expression `e` into the symbol pointer, pointed to by `b`. The type of this base is given by an `int` return code. Further on, `e->type` has to be checked to be one of the operations to handle. The section pointer `s` and the current pc `p` are needed to call the standard `find_base()` function.

33.6.2 The file `cpu.c`

A `cpu` module has to provide the following elements (all other functions and data should be `static` to prevent name clashes) in `cpu.c`:

```
int bitsperbyte;
```

The number of bits per byte of the target `cpu`. Usually 8.

```
int bytespertaddr;
```

The number of bytes per target address. Note, that this really defines the size of a backend's address pointer and might differ from the actual size of `taddr` (see above).

```
mnemonic mnemonics[];
```

The mnemonic table keeps a list of mnemonic names and operand types the assembler will match against using `parse_operand()`. It may also include a target specific `mnemonic_extension`.

```
const char *cpu_copyright;
```

A string that will be emitted as part of the copyright message.

```
const char *cpuname;
```

A string describing the target cpu.

```
int init_cpu();
```

Will be called during startup, after argument parsing. Must return zero if initializations failed, non-zero otherwise.

```
int cpu_args(char *);
```

This function will be called with the command line arguments (unless they were already recognized by other modules). If an argument was recognized, return non-zero.

```
char *parse_cpu_special(char *);
```

This function will be called with a source line as argument and allows the cpu module to handle cpu-specific directives etc. Functions like `eol()` and `skip()` from the syntax-module should be used to keep the syntax consistent.

```
operand *new_operand();
```

Allocate and initialize a new operand structure.

```
int parse_operand(char *text,int len,operand *op,int requires);
```

Parses the source at `text` with length `len` to fill the target specific operand structure pointed to by `op`. Return with one of the following codes:

PO_NOMATCH
The source did no match the operand type given in `requires`.

PO_CORRUPT
The source was definitely identified as garbage, making it useless to try matching it against any other operand types.

PO_MATCH The parsed source matches the operand type in `requires`. As soon as all the instruction's operands have been matched, the instruction is successfully recognized.

PO_SKIP Works like **PO_MATCH**, but skips the next operand from the mnemonic table. For example, because it was already handled together with the current operand.

PO_COMB_OPT
Works like **PO_MATCH**, but requests parsing of the next argument from the source text, if any, with a pointer to the same `operand` structure as before. This makes it possible to merge multiple operands into a single operand structure.

PO_COMB_REQ
Like **PO_COMB_OPT**, requests parsing of the next argument with a pointer to the same `operand` structure. But this time the additional argument is mandatory.

PO_NEXT Source did not match the given operand type in `requires`. Request parsing the same chunk of source text again, but using the following

operand type. Can be used to break a `PO_COMB_OPT` or `PO_COMB_REQ` attempt and continue normally.

```
size_t instruction_size(instruction *ip, section *sec, taddr pc);
    Returns the size of the instruction ip in bytes, which, in the final pass, must be
    identical to the number of bytes written by eval_instruction() (see below).

dblock *eval_instruction(instruction *ip, section *sec, taddr pc);
    Converts the instruction ip into a DATA atom, including relocations, if neces-
    sary.

dblock *eval_data(operand *op, taddr bitsize, section *sec, taddr pc);
    Converts a data operand into a DATA atom, including relocations.

void init_instruction_ext(instruction_ext *);
    (If HAVE_INSTRUCTION_EXTENSION is set.) Initialize an instruction extension.

char *parse_instruction(char *,int *,char **,int *,int *);
    (If MAX_QUALIFIERS is greater than 0.) Parses instruction and saves extension
    locations.

int set_default_qualifiers(char **,int *);
    (If MAX_QUALIFIERS is greater than 0.) Saves pointers and lengths of default
    qualifiers for the selected CPU and returns the number of default qualifiers.
    Example: for a M680x0 CPU this would be a single qualifier, called "w". Used
    by execute_macro().

cpu_opts_init(section *);
    (If HAVE_CPU_OPTS is set.) Gives the cpu module the chance to write out OPTS
    atoms with initial settings before the first atom for a section is generated.

cpu_opts(void *);
    (If HAVE_CPU_OPTS is set.) Apply option modifications from an OPTS atom. For
    example: change cpu type or optimization flags.

print_cpu_opts(FILE *,void *);
    (If HAVE_CPU_OPTS is set.) Called from print_atom() to print an OPTS atom's
    contents.
```

33.7 Output modules

Output modules can be chosen at runtime rather than compile time. Therefore, several output modules are linked into one vasm executable and their structure differs somewhat from syntax and cpu modules.

Usually, an output module for some object format `fmt` should be contained in a file `output/<fmt>.c` (it may use/include other files if necessary). To automatically include this format in the build process, the `OUTFMTS` definition in `make.rules` has to be extended. The module should be added to the `OBJJS` variable at the start of `make.rules`. Also, a dependency line should be added (see the existing output modules).

An output module must only export a single function which will return pointers to necessary data/functions. This function should have the following prototype:

```
int init_output_<fmt>()
```

```

    char **copyright,
    void (**write_object)(FILE *,section *,symbol *),
    int (**output_args)(char *)
);

```

In case of an error, zero must be returned. Otherwise, It should perform all necessary initializations, return non-zero and return the following output parameters via the pointers passed as arguments:

copyright

A pointer to the copyright string.

write_object

A pointer to a function emitting the output. It will be called after the assembler has completed and will receive pointers to the output file, to the first section of the section list and to the first symbol in the symbol list. See the section on general data structures for further details.

output_args

A pointer to a function checking arguments. It will be called with all command line arguments (unless already handled by other modules). If the output module recognizes an appropriate option, it has to handle it and return non-zero. If it is not an option relevant to this output module, zero must be returned.

At last, a call to the `init_output_<fmt>()` has to be added in the `init_output()` function in `vasm.c` (should be self-explanatory). Besides assigning the above mentioned function pointers, this function can be used to redefine the assembler's behaviour. For example you may set the following global variables:

```
unnamed_sections = 1;
```

Set when the output module cannot handle section names. Usually such an output module only knows section types: text, data, bss.

```
secname_attr = 1;
```

Set when the section attributes are used to differentiate between two sections with the same name.

Some remarks:

- Some output modules cannot handle all supported CPUs. Nevertheless, they have to be written in a way that they can be compiled. If code references CPU-specifics, they have to be enclosed in `#ifdef VASM_CPU_MYCPU ... #endif` or similar.
Also, if the selected CPU is not supported, the init function should fail.
- Error/warning messages can be emitted with the `output_error` function. As all output modules are linked together, they have a common list of error messages in the file `output_errors.h`. If a new message is needed, this file has to be extended (see the section on general data structures for details). When the cause for an error relates to an atom you may also use the `output_atom_error` function instead, which additionally prints the atom's source text line. In `output_errors.h` use the `NOLINE` flag when no atom is available.
- `vasm` has a mechanism to specify rather complex relocations in a standard way (see the section on general data structures). They can be extended with CPU specific

relocations, but usually CPU modules will try to create standard relocations (sometimes several standard relocations can be used to implement a CPU specific relocation). An output module should try to find appropriate relocations supported by the object format. The goal is to avoid special CPU specific relocations as much as possible.

Volker Barthelmann vb@compilers.de